

Sewing Pattern — Dress 4009

Recommendations on fabric: natural / mixed knit fabric of medium or high stretchiness

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: hem - 1.5 cm; neckline and armholes – 1.5 cm; other seam allowances - 0.8 cm. Outer and side edges of the ruche – 0 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Right front part – 1 detail
2. Left front part – 1 detail
3. Back part – 2 details
4. Ruche – 1 detail

Advice:

Knitted fabric details are sewn together with special elastic or narrow zig-zag stitch. When serging cut seam allowances to 0.6 – 0.8 cm. Seam allowance on turnup is stitched with twin needles to save stretchiness. Details also can be sewn together via 3 or 4 – threaded serger.

INSTRUCTIONS:

1. Sew darts on front part. Press depths downwards. (darts have different depth according to design).
2. Serge outer and side edges of the ruche with rolled seam. Stitch loosely along inner edge and gather ruffles. Sew right and left parts of the front, inserting the ruche between them, from the notch up to marked line of side seam.
3. Sew center edge of back part. Serge and press seams onto left side. Sew shoulder and side edges. Serge seams and press towards back part.
4. Serge seam allowances of neckline and of the armhole, turn inside and topstitch.
5. Serge hem of garment. Turn onto wrong side, press and topstitch.

TECHNICAL DRAWING: