

Sewing Pattern — Dress 5900

Recommendations on fabric: lightweight fabrics suitable for dresses

You will also need: fusible interfacing, elastic thread, 2 buttons

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: hem of the garment – 1.5 cm; other seam allowances - 1 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric:

1. Back –cut 2
2. Front – cut 1 on fold
3. Neck/Facing – cut 2

Fusible interfacing:

1. Facing – cut 1

INSTRUCTIONS:

1. Apply interfacing to outer facing.
2. Serge center back edges separately. Sew center back seam from the notch downwards, press seam apart, pressing the slit. Topstitch slit edges at 0.1 cm.
3. Sew side seams. Serge and press seam toward back.
4. Serge edges of armholes, press onto wrong side, and topstitch.

5. Buttonhole loops: Cut a strip of bias tape 2.5 cm wide and 10 cm long. Fold bias tape in half lengthwise, right sides together and sew at 0.3 cm from the fold. Cut off seam allowances close to the stitch, turn bias tape right side out and straighten. Cut 2 buttonhole loops. Each loop is 4 cm long.
6. Pin facing right sides together, and sew along neckline edge, sew center back edges inserting the buttonhole loops at the same time. Trim seam allowances. Turn right side out and press. Press lower edges onto wrong side between marks. Sew top edges of back and front to lower facing according to marking. Sew top facing into the edge of lower facing. Press.
7. Serge bottom edge of garment, press onto wrong side, and topstitch.
8. Topstitch elastic thread according to marking. Sew buttons on the facing.

TECHNICAL DRAWING:

