

Sewing Pattern — Dress 5214

Recommendations on fabric: silk crepe of 150 cm width.

You will also need: lining; fusing; decorative braid with beads;
1 zipper.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Strap – 1 piece
2. Upper front part – 1 piece
3. Middle front part – 1 piece
4. Lower front part – 1 piece
5. Side front part – 1 piece
6. Right back part – 1 piece
7. Left back part – 1 piece

Lining:

5. Side front part – 1 piece
6. Right back part – 1 piece
7. Left back part – 1 piece

Also cut out seamless front part: scotch paper patterns of upper front part, middle front part and side front part, creating a dart near the armhole.

Cut lining details mirror to fabric details!

Fusing: Apply fusing stripe of 2 cm width to wrong side of lining neckline and armholes.

INSTRUCTIONS:

1. Sew upper front and middle front and lower front taking into account marks. Sew side part leaving a slit.
2. Sew back darts, middle back seam leaving a slit for the zipper. Neaten seam allowance and press them apart; press closure slit edges. Sew the zipper in under slit edges with its teeth hidden.
3. Sew side seams.
4. Sew darts and seams of lining details leaving shoulder seam unstitched. Press shoulder seam allowance to wrong side.
5. Coincide lining and fabric garment right sides together and overstretch it along armholes and neckline, begin and stop stitching at shoulder seam. Fold the lining out and topstitch it on overstretching seam; press. Fold lining closure slit allowance under and sew to zipper braid.
6. Sew garment shoulder seam. Into lining, sew shoulder seam by hand.
7. Fold the hem under, so that lining hem was 1 cm shorter than fabric one. Fold the lining to right side along one of slit edges, and pin to the garment along slit edge. Fold garment hem allowance to right side and pin it on lining along slit edge. Sew the lining. Fold hem allowance of garment and lining to wrong side and press it. Overstretch another edge of slit with lining and allowance in the same way. Sew the hem with blind stitch.
8. Fold the strap along the center and sew to 0.5 cm width. Sew strap front end above front relieve. Put the dress on, adjust garment length and sew strap back end under back décolleté.
9. Sew decorative braid on strap, on relieve to slit and on front seams.

TECHNICAL DRAWING:

