

Sewing Pattern — Blouse 5060

Recommendations on fabric: silk/cotton/viscose

You will also need: fusing; 12 small buttons

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Front part – 2 pieces
2. Back part – 1 folded piece
3. Collar – 2 folded pieces
4. Sleeve – 2 pieces
5. Cuff – 2 pieces

Additionally: 2 piping for sleeve slits (16 cm length and 2.5 cm width including allowances).

Fusing:

1. Collar – 1 folded piece
2. Front band – 2 pieces
3. Cuff – 2 pieces

INSTRUCTIONS:

1. Stitch darts, stitch side/shoulder seams.
2. Turn in hem allowances and topstitch.

3. Topstitch the collar along outer contour, tack open edges together and tack the collar into neckline. Fold one-piece front bands into right side and stitch to neckline edge catching the collar; stitch the collar into back neckline with the same stitch. Make several slashes into front seam allowances' rounding. Fold front bands into wrong side. Cut collar/back neckline joining seam allowances close to the stitch, neaten them together and press downward. Sew front bands to blouse lower edge and to shoulder seam allowances. Topstitch the blouse along front edgings and along front upper edges up to the seam joining the collar.

4. Make slits into sleeves and lay slits as straight lines. Lay the piping on the sleeve right sides together and stitch one of piping's long edges close to slit edge, especially at seam center point (slit top). Press the piping toward the slit above joining seam, fold it to 0.7 cm width and sew above joining seam. Stitch edging's both parts diagonally at wrong side near slit top. Fold slit front edge's edging into wrong side and tack it to sleeve hem. Stitch sleeve seam.

5. Tack pleats into sleeve hems. Stitch outer cuff to sleeve hem, fold inner cuff upward. Fold inner cuff under and sew it above cuff joining seam. Topstitch the cuff.

6. Stitch sleeves in easing them along sleeve caps.

7. Make buttonholes into front right edging, make buttonholes into cuffs. Sew buttons.

TECHNICAL DRAWING:

