

Sewing Pattern — Coat 5019

Recommendations on fabric: fabric suitable for coats of 150 cm width

You will also need: lining; fusible interfacing; 4 buttons; shoulder pads

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 3 cm on garment hem; 4 cm on sleeve hem; 1 cm on all other seams

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric:

1. Collar – cut 2
2. Center front – cut 2
3. Flap (pocket's off-set welt) – cut 4
4. Center back – cut 2
5. Side back – cut 2
6. Side front – cut 2
7. Back neck facing – cut 1 on fold
8. Upper sleeve – cut 2
9. Lower sleeve – cut 2

Lining:

10. Pocket sacking – cut 4
11. Center front – cut 2 (excluding width of front self-facing)
12. Center back – cut 2
13. Side back – cut 2
14. Side front – cut 2
15. Upper sleeve – cut 2
16. Lower sleeve – cut 2

Fusible interfacing: Apply the interfacing to wrong side of front self-facings, back neck facing, lower edges of off-set welts. Additionally, apply a strip to hem allowance.

INSTRUCTIONS:

1. Neatly process pocket off-set welts, topstitch edges at 1 cm distance. Lay off-set welt on center front in accordance with notches; then lay one of sackings on the welt and topstitch on pocket entrance. Lay another sacking on side front and topstitch also. Turn sackings onto wrong side, sew front and side front seams under/over pocket entrances. Sew sackings' edges together from pocket entrances marks (from inside). Press front/side front seam allowances toward center front. Topstitch seam at 1 cm distance. Topstitch short edges of off-set welts strictly along decorative stitch on front.
2. Sew center back seam downward to vent mark, press the seam apart. Press vent seam allowance toward left.
3. Sew sides backs to center back, press seams apart. Sew shoulder seams and side seams, press seams apart. Sew back neck facing to front self-facing, press seams apart.
4. Fold front self-facing onto right side, topstitch neckline up to the mark. Snip neckline allowance close to the mark, trim corners and understitch where possible. Turn front self-facings onto wrong side. Pin collar right sides together, and sew outer edge. Clip into curves, trim corners, and turn right side out. Sew outer collar to neckline, right sides together. Sew inner collar to facing. Press seam allowances apart. Press allowances of seams joining inner collar and back neck facing apart and topstitch along joining seam.
5. At the hem: turn front self-facing onto right side. Sew lower edge of facing. Turn facing onto wrong side. Press garment hem allowances onto wrong side and hem by hand.
6. Press vent left edge onto wrong side, sew to hem allowance. Press self-facing of right side of vent onto wrong side, sew to hem allowance. Pin the vent along matching lines. Topstitch left back at vent's top along marking catching vent's edges.
7. Sew sleeve seams, press seams apart. Make a gathering stitch along sleeve cap for ease. Sew sleeves into armholes, matching marks and adjusting ease.
8. Sew in shoulder pads.
9. Sew lining together same as main fabric. Sew the lining to sleeve hems, and inner edges of facing. Pin the lining at vent segment carefully. Cut the lining at vent segment; do not forget about seam allowances! Fold lining hem under, and sew to vent edges. Fold and topstitch hem of lining a few cm shorter than garment.
10. Make buttonholes in right front, sew buttons on left one.

TECHNICAL DRAWING:

