

Sewing Pattern — Dress 4168

Recommendations on fabric: natural / mixed stretch-knit fabric of 2 colors

You will also need: stretch bias tape, or cut your own from fabric - 4cm wide

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: on hem of the dress and of sleeve – 2 cm, all other seams 0.7 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric 1:

1. Center front- cut 1 on fold
2. Center back– cut 2
3. Sleeve - cut 2

Fabric 2:

1. Side front - cut 2
2. Side back - cut 2

INSTRUCTIONS:

1. Sew side fronts to center front and side backs to center backs. Serge seams and press toward center.
2. Sew center back seam. Serge seam and press toward left.
3. Sew right shoulder seam. Serge and press seam toward back.
4. Cut a strip of bias tape of length equal to neckline length. Fold bias tape in half lengthwise, wrong sides together and press. Pin the bias tape to neckline edge, right sides together, and sew. Trim seam, turn and press bias tape onto wrong side, topstitch along the fold onto main detail, press. Sew left shoulder seam. Serge and press toward back.

5. Serge lower edge of sleeve, turn inside and topstitch. Sew sleeve into armhole, matching notches. Fold bias tape in half lengthwise, wrong sides together, and press. Pin the bias tape to edge of the armhole from right side and sew. Trim seam and turn the bias tape onto wrong side, topstitch along the fold onto main detail. Press seam.
6. Sew side seams. Serge and press toward back.
7. Serge bottom edge of dress, turn onto wrong side, and topstitch.

TECHNICAL DRAWING:

