

Suit (Jacket) - Sewing Pattern #6052

Recommendations on fabric: natural/mixed suiting fabrics.
you will also need: lining; fusible interfacing; 2 buttons.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

1. back - cut 2
2. side - cut 2
3. patch pocket - cut 2
4. center front facing - cut 2
5. front - cut 2

- 6. collar - cut 2
- 7. upper sleeve - cut 2
- 8. lower sleeve - cut 2

Lining:

- 1. back - cut 2
- 2. side - cut 2
- 7. upper sleeve - cut 2
- 8. lower sleeve - cut 2
- 9. front lining - cut 2

fusible interfacing: front, center front facing, collar.

INSTRUCTIONS:

Apply fusible interfacing to collars, fronts, Center Front facings.

Sew darts on front. Sew side to front.

Fold the upper edges of pockets onto wrong side, press and topstitch.

Fold inside the raw edges of pockets and press, pin pockets onto front according to markings and topstitch.

Sew center back seam. Sew princess seam on back up to vent corner, press seam allowances towards back. Turn the left seam allowance on vent onto right side, sew along the hem line, turn right side out and press. Topstitch along the edge of the left side of vent. Fold the hem seam allowance on right side of vent onto right side, sew along the edge of seam allowance, turn right side out and press. Place vent onto Side, and sew a slanted fixing stitch at the top of the vent . Fold inside the seam allowances along hem and press.

Sew shoulder seams.

Sew upper sleeves to lower sleeves. Sew sleeves into armholes. Fold inside the seam allowances along hem and press. Sew on shoulder pads.

Sew Center Front facings to the linings of Fronts, and sew pieces of linings in the same way as pieces from the main fabric.

Pin lower collar to the neckline on main piece, right sides together, and sew. Sew the upper collar into the neckline on lining. Pin main piece to lining and sew around: start at 3 cm from the center corner on front, sew around center front edges and around collar. Turn right side out, press. Slipstitch the lower edge of upper corner to the back neckline on main fabric.

Fold under the lower edge of lining on jacket and on sleeves and sew by hand with invisible stitches to the lower edge of the main piece.

On left front make buttonholes. On right front sew on buttons.

TECHNICAL DRAWING:

