

Sewing Pattern — Trousers 6038

Recommendations on fabric: cotton or bologna fabric or poplin of 150 cm width

You will also need: lining; fusing; wide elastic braid; eyelets; a cord

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Waistband – 1 piece
2. Pocket – 2 pieces
3. Upper front part – 2 pieces
4. Side front part – 2 pieces
5. Lower front part - 2 pieces
6. Upper back part – 2 pieces
7. Lower back part – 2 pieces

Lining:

1. Upper pocket sacking – 2 pieces

Fusing: button catch, waistband.

INSTRUCTIONS:

Apply the fusing to wrong side of waistband and button catch.

Press pocket allowances to wrong side, then topstitch pocket entrance and decorative stitches along the pocket lower edge. Lay pockets on the upper front parts and topstitch along the perimeter (excepting pocket entrance).

Stitch the sacking and the garment along the pocket entrance, right sides together. Turn them right side over, then press and stitch. Lay the front part on the side part, make sackings equal, then stitch edges. Sew sackings and waist edge of trousers.

Sew front middle seam, press to left, then make a decorative stitch.

Sew side and inside leg seams. Sew back middle seam.

Sew trousers lower edges "in a ring". Coincide them with upper parts right side together, then stitch. Make pleats into trousers, then stitch.

Sew the waistband to trousers upper edge. Press the waistband along the center, then turn waistband inner edge and topstitch it along the joining seam, leaving a slit unstitched. Pull the elastic braid into the waistband, fix it according to marks. Sew the unstitched place.

Make eyelets on lower parts of the garment. Press the hem inside, then topstitch. Pull the cord into eyelets.

TECHNICAL DRAWING:

