

Sewing Pattern — Dress 4150

Recommendations on fabric: fabric suitable for dresses

You will also need: blind zipper; fusing; decorative fastener

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: all seams 1 cm. lower edge – 2.0 cm, along vent – 6 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.

ATTENTION! Legend on patterns is made on right side



CUTTING:

Fabric:

1. Back yoke - 1 detail
2. Middle part of back part – 1 detail
3. Side back part – 2 details
4. Inset of back part - 1 detail
5. Lower back part - 2 details
6. Lower front part – 1 detail
7. Side front part - 2 details
8. Left middle part of front part– 1 detail
9. Right middle part of front part– 1 detail
10. Yoke of front part - 2 details
11. Stand-up part of collar - 2 details
12. Sleeve - 2 details
13. Cuff - 2 details
14. Belt — 1 detail
15. Bolt loop — 1 detail

Fusing:

1. Stand-up part of collar - 1 detail
2. Cuff - 2 details

INSTRUCTIONS:

1. Apply fusing to details of stand-up part of collar, cuffs and one-piece buttonstands.
2. Sew relieve seams on back part, press seam allowances towards center and serge. Stitch yoke to back part, press seam onto yoke and serge.
3. Sew darts on lower parts of back part, press depths towards center. Cut 5 cm on left lower part of back part along vertical vent edge. Apply fusing to vent on both details of lower back parts from wrong side. Mark a middle seam line from right side (vent fold line). Press left part along vent fold line, press only seam allowance of right side of the vent (6 cm) on right part onto wrong side. Coincide parts on middle seam and fix on upper vent edge. Serge middle edge of back part separately on each detail. Serge vent seam allowances. Sew middle edge from top to vent corner. Slash vent corner seam allowance on right part. Press seam allowances of middle seam apart, press seam allowances of vent and fix them with machine stitch.
4. Stitch inset of back part to lower part, press seam onto inset and serge. Sew top and lower parts of back part, press seam allowances downwards and serge.
5. Sew relieve edges of front part, press seam allowances towards center and serge. Stitch yokes to front parts, press seam onto yoke and serge. Serge inner edges of one-piece buttonstands.
6. Press one-piece buttonstand on left part of front part onto right side and overstitch top corner. Slash seam allowances in neckline corner, turn buttonstand onto wrong side, press. Topstitch buttonstand on front part along marked line.
7. Press one-piece buttonstand on right part of front onto right side and overstitch top corner. Slash seam allowances in neckline corner, turn buttonstand onto wrong side, press. Put right front part on left, leveling inner edge of right buttonstand with bias edge of left front part. Topstitch right buttonstand on marked line, fixing right and left front parts.
8. Sew top and bottom front parts, press seam allowances downwards and serge.
9. Sew shoulder seams, press seam onto back part and serge. Sew right side edge, press seam onto back part and serge. Serge separately left side edges. Sew left side edge from armhole up to marker and from marker up to hem, press seam allowances apart. Sew in zipper.
10. Fold stand-up part of collar details right sides together and overstitch ends and outer edge of collar. Start and finish the stitch exactly near marked line of collar connecting seam. Slash seam allowances in corners, slash on rounded parts. Turn collar out, straighten and press.
11. Sew outer stand-up part of collar into the neckline, slash seam allowances and press onto stand-up part of collar. Turn open edge of inner stand-up part of collar and topstitch into connecting seam.
12. Sew edge of sleeve, press seam allowances and serge.
13. Sew cuff into ring, press seam allowances apart. Fold cuff in half lengthwise wrong sides together. Fold cuff with wrong side of sleeve and stitch. Press seam allowances and serge. Turn cuff onto right side.
14. Sew sleeve into armhole, leveling notches, press seam allowances and serge.
15. Serge lower edge of the garment, press onto wrong side and topstitch.
16. Serge one long edge of bolt loop. Fold bolt loop in three layers and topstitch on long sides. Cut belt loop into 3 details. Sew bolt loops on waist level on back part center and on side seams.
17. Fold belt in half lengthwise right sides together and overstitch on long and short sides. Turn belt out and press, serge short edge. Run serged edge of the belt into fastener and topstitch.

TECHNICAL DRAWING:

