

Sewing Pattern — Dress 7102

Recommendations on fabric: natural/mixed fabric;

You will also need: zipper; piping; elastic braid.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

SEAM ALLOWANCE: 1 cm. for all seams

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Front part – 1 piece
2. Back part – 2 pieces
3. Front skirt – 1 piece
4. Front underskirt – 1 piece
5. Back skirt – 2 pieces
6. Back underskirt – 2 pieces
7. Pocket – 2 pieces

INSTRUCTIONS:

1. Neaten the pocket along the contour, fold into wrong side and stitch at 1.5 cm from the bending. Pull the elastic braid in and gather pocket's upper edge. Fix braid's ends. Press pocket's lower/side edges into wrong side.
2. Topstitch pockets on front skirt.
3. Stitch side edges of skirt and underskirt, neaten them and press.
4. Neaten hems of skirt and underskirt. Fold hems under and topstitch.

5. Stitch side/shoulder edges of the dress, neaten seams and press then backwards.
6. Lay the skirt on the underskirt right sides together, adjust upper edges and fix it. Make a loose stitch along upper edge at 0.5 cm from the edge. Pull upper edges according to front/back part's lower edges.
7. Neaten middle back edge and stitch it up to closure's notch. Press middle back seam apart pressing closure slit. Stitch the zipper in.
8. Trim the neckline and armholes with the piping. Press the neckline and armholes.
9. Neaten skirts' hems, fold them under and topstitch. Press the hems.

TECHNICAL DRAWING:

