

Sewing Pattern — Blouse 7074

Recommendations on fabric: sheer natural fabric

You will also need: fusible interfacing; piping; decorative cord.

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

SEAM ALLOWANCE: 1 cm for all seams, 2 cm for hem, 0 cm for shaped neckline.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

Fabric:

1. Upper back part – 1 piece
2. Lower back part – 1 piece
3. Upper front part – 1 piece
4. Lower front part – 1 piece
5. Back facing – 1 piece
6. Front facing – 2 pieces
7. Sleeve – 2 pieces

Interfacing: front/back facings.

INSTRUCTIONS:

1. Apply the interfacing to front/back facings.
2. Stitch upper front darts. Press darts to center back part.
3. Press inverted pleat into lower front part. Fix the pleat top with 3-cm stitch at 0.5 cm from upper edge.

4. Press neckline piping along the center. Overstitch neckline with piping. Fix the piping at the corner with 1-cm stitch at neckline lower point.
5. Stitch lower front part to upper front part. Neaten joining seam and press it. Stitch lower back part to upper back part.
6. Stitch side/shoulder edges. Press side/shoulder seams backwards.
7. Neaten sleeve edges and stitch them leaving hem slits. Press sleeves seams apart pressing slits. Make decorative stitch at 0.5 cm from slit edge. Neaten sleeves hems and press them into wrong side. Topstitch sleeve hems at 0.7 cm distance.
8. Stitch sleeves into armholes. Neaten joining seams.
9. Stitch shoulder edges of front/part facings. Neaten facing outer edge and front facing middle edge.
10. Overstitch front/back necklines edges with facings. Topstitch joining seam allowance at 0.2 cm distance. Press facing into wrong side making an edging. Fold front facing middle edge under and topstitch the facing at 0.7 cm from neckline edge.
11. Cut decorative cord according to size and pull it into sleeve hems and front/back necklines holes.
12. Neaten blouse hem, fold it under and topstitch.

TECHNICAL DRAWING:

