

Sewing Pattern — Blouse 4395

Recommendations on fabric: fabric suitable for blouses with lycra.

You will also need: fusible interfacing, ribbon with snaps.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: on hem — 2 cm, all other seams - 1 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

(On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Fabric:

- 1. Back cut 2
- 2. Left front cut 1
- 3. Right front cut 1
- 4. Left front band facing cut 1
- 5. Right front band facing cut 1
- 6. Belt cut 2
- 7. Sleeve cut 2
- 8. Cuff cut 2
- 9. Collar cut 2
- 10. Collar stand-cut 2

Interfacing:

- 1. Collar cut 1
- 2. Collar stand cut 1
- 4. Left front band facing cut 1
- 5. Right front band facing cut 1
- 6. Cuff cut 2



INSTRUCTIONS:

- 1. Apply fusible interfacing to listed pieces.
- 2. Place collars right sides together. Stitch ends and fall parts of collar. Trim seams. Turn collar out, straighten and press. Place collar stands right sides together, insert ready collar between them, level notches and sew, stitching the ends of collar stand at the same time. Turn ready collar out and press.
- 3. Fold belt details in half lengthwise, right side inside and stitch long and one short sides. Trim seams in corners, turn belt right side out, straighten, press.
- 4. Mark and sew bust, waist and shoulder farts on front and back. Press bust darts upwards, waist and shoulder darts toward center. Make and fasten pleats on right front (dart edges are directed upwards).
- 5. Sew middle edge of back. Serge seam and press it toward left side edge.
- 6. Sew shoulder and side edges inserting belt into left side edge. Serge seams and press toward back.
- 7. Serge shoulder edges and inner edges of front band facings. Baste collar into neckline. Place front band facings and garment right sided together, insert right side of the belt and stitch: left front band from hem to shoulder edge, slash inner collar stand near the shoulder edge and sew into neckline only outer stand collar up to right shoulder edge, slash collar stand near the right shoulder edge, turn back and sew right front band down to hem. Clip seam allowances on curves, trim in corners. Turn front band facings wrong side out, straighten and press. Turn inside unfinished edge of inner collar stand and topstitch into connecting seam.
- 8. Sew and serge sleeve edges. Sew sleeves into armholes, press and serge.
- 9. Fold cuffs in half lengthwise and stitch short sides. Turn cuffs out and press. Sew cuff to hem of sleeve, placing the joint of cuff sides at the notch. Press and serge seam allowances.
- 10. Press hem to wrong side at 1 cm, then again at 1 cm and topstitch.
- 11. Topstitch ribbon with snaps onto fronts.

TECHNICAL DRAWING:

