

Sewing Pattern — Dress 4288

Recommendations on fabric: fabric suitable for dresses

You will also need: lining, blind zipper

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowances: all seams - 1 cm; along the vent – 6 cm;
hem of the dress - 2.0 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Central upper back part - 2 details
2. Side upper back part - 2 details
3. Central lower back part - 2 details
4. Side lower back part - 2 details
5. Central upper front part - 1 detail
6. Side upper front part - 2 details
7. Lower front part - 1 detail
8. Basque - 4 details
9. Sleeve - 2 details
10. Bow – 1 detail
11. Strap – 1 detail

Lining:

1. Central upper back part - 2 details
2. Side upper back part - 2 details
3. Central upper front part - 1 detail
4. Side upper front part - 2 details
5. Sleeve - 2 details

INSTRUCTIONS:

1. Sew darts on lower front part, press depths towards center. Sew darts on central upper back part, press depths towards center.
2. Sew princess edges on upper details of back part / front part. Press seam allowances towards center and serge. Sew side and shoulder edges of upper part, press seam onto back part and serge.
3. Fold details of basque right sides together and overstretch outer edge. Turn detail right side out, straighten, press.
4. Sew princess edges of lower back part, inserting the basque. Press seam allowances towards center and serge. Sew side seams of lower part, press seam onto back part and serge. Fix basque to lower part of the dress along top edge.
5. Fold strap detail in half lengthwise right sides together and overstretch long edge. Turn detail right side out, press, placing the seam in the center of detail. Serge one of the sides. Fold bow detail in half lengthwise right sides together and overstretch edges, leaving a slit. Turn detail right side out, press, sew the slit. Stitch loosely across the bow and gather slightly.
6. Sew upper and lower parts of the dress, inserting the strap with unserged side, press seam allowances upwards and serge. Turn serged edge of the strap inside and stitch to front part. Run the bow through the strap and fasten.
7. Cut 5 cm off on left central lower back part along vertical edge of the vent. Apply fusing to wrong side of the vent on both details of central lower back part. Mark center seam line (vent fold line) on the right side. Press left part along vent fold line, on right part press only seam allowance of right side of the vent (6 cm) onto wrong side. Align details along center seam and fix along top edge of the vent. Serge center edge of back part separately on each detail. Serge seam allowances of the vent. Sew center edge of back part from closure marker up to vent corner. Slash away vent corner seam allowance on right part. Press apart seam allowances of center seam, press seam allowances of the vent and fix them along right side with machine stitch. Sew zipper in.
8. Fold the sleeve with lining right sides together and overstretch lower edge. Turn the sleeve right side out, press. Sew the sleeve into armhole, leveling notches. Press seam allowances.
9. Sew details of lining the same way as main fabric details. Serge lower edge. Fold the dress with lining right sides together, leveling neckline edges. Fold lining aside, leaving 5 mm to blind zipper edges and pin to top edge of the dress. Fold seam allowances along zipper onto right side of the dress and pin to neckline edge on top of lining. Overstretch neckline edge. Slash seam on rounded parts, turn details out and press. Topstitch seam allowances onto lining. Fasten lining to zipper tape. Overstretch edges of armholes, slash seam allowances, turn detail right side out, press. Fix lower edge of lining to the dress.
10. Serge seam allowance of the dress hem, press onto wrong side and undersew with invisible stitches.

TECHNICAL DRAWING:

