

## Sewing Pattern — Coat 4497

Recommendations on fabric: well draping natural or mixed fabric suitable for coats.

You will also need: 3 buttons, fusible interfacing, lining, shoulder pads, sleeve heads.

Seam allowances: hem of coat and sleeve – 3 cm, other seams – 1 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.

- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



### **CUTTING:**

#### **Main fabric:**

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front – cut 2
5. Lower back – cut 2
6. Lower front – cut 2
7. Front facing – cut 2
8. Back neck facing – cut 1
9. Upper sleeve – cut 2
10. Lower sleeve – cut 2
11. Hood – cut 2

#### **Lining:**

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front – cut 2
5. Lower back – cut 2
6. Lower front – cut 2
7. Upper sleeve – cut 2
8. Lower sleeve – cut 2
9. Hood – cut 2

Fusible interfacing: center front, front facing, back neck facing, hem of sleeve.

**Note:** front, back and hood lining details are cut on main fabric pattern pieces excluding the width of front facings, back neck facing.

### **INSTRUCTIONS:**

1. Apply fusible interfacing to listed pieces.
2. Sew darts on back and press them toward center. Sew side and front backs / fronts. Press apart seams. Sew center seam on upper and lower backs. Press apart seam.
3. Sew side edges on upper and lower parts of the coat. Press apart seams. Sew shoulder edges. Press apart seams. Sew upper and lower parts. Press apart seam. Serge lower edge.
4. Sew hood edge. Press apart seam. Sew hood edge on lining detail. Press seam to left side. Stitch outer edge with lining. Fasten on lower edge and then sew as one detail.
5. Sew and press apart shoulder edges of back neck facing and front facing. Sew in hood into neckline.
6. Place front facing onto front right sides together, pin and stitch round-wise front band and neckline leaving the hood between main fabric and facing edges. Trim seam in corners. Turn front bands out, straighten and press.
7. Sew and press apart elbow edge of the sleeve. Press hem of sleeve. Sew and press apart front edge of sleeve.
8. Sew sleeves into armholes matching notches and easing in on curves. Sew shoulder pads and sleeve heads.
9. Sew seams on lining details and sew in sleeves. Serge, turn inside and topstitch hem of lining.
10. Sew lining to inner edges of front bands and back neck facing. Sew lining to hem of sleeves. Turn coat out through the opening in sleeve. Sew the opening closed.
12. Turn inside hem of the coat and topstitch.
13. Serge buttonholes on right front. Sew on buttons on left front.

**TECHNICAL DRAWING:**

