

Sewing Pattern —Dress 4504

Recommendations on fabric: natural or mixed dress fabric.

You will also need: invisible zipper, fusible interfacing.

Seam allowances: all seams - 1 cm, hem of dress and sleeves – 2 cm, along vent – 6 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.

- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Main fabric:

1. Back – cut 2
2. Upper right front – cut 1
3. Upper left front – cut 1
4. Front insert – cut 1
5. Lower front – cut 1
6. Stand collar – cut 4
7. Right front facing – cut 1
8. Left front facing – cut 1
9. Sleeve – cut 2

Fusible interfacing:

1. Stand collar – cut 1
2. Right front facing – cut 1
3. Left front facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing to listed pieces.
2. Sew waist and bust darts on backs, press darts toward center.
3. Sew outer stand collars into back neckline, trim seams, press them onto collar.
4. On left part of back, along vertical vent edge, cut off 5 cm. Apply fusible interfacing to wrong side of the vent on both backs. On right side mark center seam line (vent fold-line). Press left part along vent fold-line, on right part press to wrong side only seam allowance of right side of the vent (6 cm). Align details on center seam and pin on upper edge of the vent. Serge center back seam separately on each detail. Serge vent allowances. Sew center back edge from mark down to vent corner. Trim away corner on right part. Press apart center back seam, press vent allowances and fasten them on right side with machine stitch. Sew in zipper.
5. Sew dart on upper right front and press it toward center. Serge lower edge of right front facing, place it onto upper front and stitch upper edge. Turn facing to wrong side and press.
6. Make and fasten pleats on upper left front, fold edges are directed downwards. Place left front facing onto upper left front and stitch on upper edge. Clip on curves, turn facing to wrong side, straighten and press.
7. Place upper left front onto right front. Match lower edge of left front with lower edge of right part facing and sew. Serge seam. Topstitch right facing onto left front, turning back right front.
8. Sew front insert to lower front, press seam upwards and serge. Sew upper and lower fronts, press seam upwards and serge.
9. Sew side edges, press seams to back and serge.
10. Press to wrong side lower allowance of inner stand collar. Place inner and outer stand collars right sides together and stitch upper edge exactly to marked line of shoulder seam. Trim seams.
11. Sew shoulder edges, placing them between inner and outer stand collars. Press seams onto back and serge. Turn details right side out. Topstitch inner stand collar into outer collar connecting seam.
12. Sew sleeve edge. Press and serge seams. Sew in sleeves, matching notches and easing in on curves. Press and serge seams.
13. Serge hems, press to wrong side and slipstitch. Tack vent allowance to hem turnup.

TECHNICAL DRAWING:

