

Sewing Pattern — Jacket 4108

Recommendations on fabric: costume fabrics of natural or mixed fibers.

You will also need: fusing; 1 button; lining

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Upper front part – 2 details
2. Lower front part – 4 details
3. Upper back part – 2 details
4. Lower back part – 4 details
5. Sleeve – 2 details
6. Cuff – 2 details
7. Buttonstand – 2 details
8. Back neckline facing – 1 detail

Lining:

1. Front part – 2 details
2. Back part – 2 details
3. Sleeve – 2 details

Fusing: buttonstand, back part neckline facing, cuffs

INSTRUCTIONS:

1. Apply fusing to buttonstand, back neckline facing, cuff.
2. Sew darts on front part and back part. Press depths towards center. Sew middle edge of back part. Press apart the seam.
3. Sew side and shoulder edges. Press seam allowances towards back part. Sew middle edge and side edges on lower parts of jacket. Stitch lower parts to front part and back part. Press apart the seam.

4. Sew edge of sleeve. Press apart the seam. Fold cuff in half lengthwise and overstretch short sides. Stitch cuff to the sleeve, leveling the notch to cuff seam. Sew sleeve into armhole.
5. Cut a bias tape of 3 cm wide, and as long as button diameter plus 2 cm. Fold bias tape in half lengthwise and put the stitch on 0.3 off the fold. Cut seam allowances and turn onto right side. Fix loop buttonhole on right front part at lower part connecting seam level.
6. Sew darts on lining details. Sew side and shoulder edges. Sew in sleeve, leaving a slit in right seam of sleeve.
7. Sew and press apart shoulder edges of buttonstands and facing. Sew buttonstand and the facing into lining of jacket. Press seam allowances onto lining. Sew middle and side edges of lower parts. Stitch lower part/s to lining. Facing/buttonstand положить onto right side of front part right side downwards and overstretch along buttonstand, along neckline and along the lower edge. Overstretch on front part side. Stitch lining to inner edge of cuff. Turn jacket through the slit in sleeve. Sew slit in sleeve. Put fixing stitch into cuff connecting seam.
8. Sew on button.

TECHNICAL DRAWING:

