

Sewing Pattern — Blouse 4100

Recommendations on fabric: natural or mixed knitted fabric of middle stretchiness / natural or mixed silk fabrics

You will also need: fusing

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: along the blouse hem - 2 cm, all other seams - 1 cm .

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Knitted fabric:

1. Front part – 1 folded detail
3. Back part – 1 detail
5. Cuff – 2 details

Silk fabric:

1. Sleeve – 2 details
2. Stand-up part of collar – 2 details
3. Right panel – 2 details
4. Left panel – 2 details

Fusing:

1. Stand-up part of collar – 1 detail
2. Right panel – 1 detail
3. Left panel – 1 detail

Advice:

Knitted fabric details are sewn together with special elastic or narrow zig-zag stitch. When serging cut seam allowances to 0.6 – 0.8 cm. Seam allowance on turnup is stitched with twin needles to save stretchiness. Details also can be sewn together via 3 or 4 – threaded serger.

INSTRUCTIONS:

1. Apply fusing to top details of stand-up part of collar, of right and left panels.
2. Sew shoulder and side edges. Serge and press towards back part.
3. Sew edge of sleeve, serge and press onto back part of sleeve. Stitch loosely on hem of sleeve and gather ruffles. Sew cuff into ring. Fold it in half lengthwise and press. Stitch cuff to the sleeve, serge. Sew sleeve into armhole. Serge.
4. Stitch loosely on front part neckline and gather ruffles. Fold details of left panel right sides together and overstitch along neckline edge. Turn onto right side and press. Fold details of right panel right sides together and overstitch along neckline edge, inserting left panel. Turn onto right side and press. Sew panel into the neckline, serge.
5. Fold details of stand-up part of collar right sides together and overstitch on top edge. Start and finish the stitch exactly near marked line of collar. Turn onto right side and press. Sew outer stand-up part of collar into the neckline. Turn seam allowance of inner stand-up part of collar inside onto wrong side and topstitch into outer stand-up part of collar connecting seam.
6. Serge lower edge of the blouse. Turn seam allowance inside and topstitch.

TECHNICAL DRAWING:

