

Sewing Pattern — Blouse 4286

Recommendations on fabric: natural or mixed blouse fabric

You will also need: Fusible interfacing, invisible side zipper, 2 buttons

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowances: all seams - 1 cm, lower edge of back part and of front part – 1.5 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric:

1. Back - cut 2
2. Front - cut 1
3. Collar - cut 1 on fold
4. Sleeve – cut 2
5. Cuff – cut 2

Fusible interfacing:

1. Cuff – cut 2

INSTRUCTIONS:

1. Apply interfacing to cuffs.
2. Sew shoulder, waist, and bust darts on backs and fronts. Press waist and shoulder darts towards center. Press bust darts toward hem.

3. Sew center seam of back, serge, and press seam toward left side.
4. Sew shoulder seams, serge, and press toward back.
5. Serge separately left side edges. Sew left side seam from the edge of the armhole down to the first notch and from second notch down to hem. Press apart the seam, including the opening for the zipper. Sew in zipper. Sew right side seam, serge and press seam toward back.
6. Fold collar in half lengthwise, right sides together, and sew ends up to marker "o". Clip seam allowances near the marker, trim corners, turn collar right side out, straighten, press. Sew outer collar into the neckline, clip into curves and trim corners. Turn seam allowance of inner collar inside and topstitch into connecting seam.
7. Cut bias tape about 18.3 cm to face the slit for the cuff opening of sleeve. Mark a line on the sleeve, cut the sleeve along the line. Open up the slit lengthwise. Sew the bias tape along the opening, stitching close to edge, and closer to the top point of the slit. Turn and press bias tape to inside. Topstitch. Serge edge of sleeve.
8. Fold cuff in half lengthwise, right sides together, and sew side edges. Start and finish the stitch exactly near marked line of cuff connecting seam. Turn cuffs right side out, press. Stitch outer side of cuff to the sleeve, turn inside seam allowance of inner side of cuff and topstitch into outer cuff connecting seam.
9. Make a gathering stitch along cap of sleeve. Gather fullness and sew sleeve into armhole, matching notches. Serge seam allowances and press toward garment.
10. Make buttonholes and sew buttons on cuffs.
11. Serge lower edge, press under and topstitch hem.

TECHNICAL DRAWING:

