

## 4697 - Sewing Pattern #4697

Recommendations on fabric: natural/mixed soft thin stable double-sided fabrics suitable for coats.

You will also need: 2 buttons.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment, seam allowance along center fronts, seam allowance along collar fall - 0 cm. Seam allowance along pocket opening – 1.5 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Back – cut 2
2. Front – cut 2
3. Sleeve – cut 2
4. Pocket – cut 2
5. Cuff – cut 2

## INSTRUCTIONS:

1. Sew center back seam, after having pinned the pieces wrong sides together. Press seam apart. Press towards left and topstitch.
2. Sew darts on front. Press bulk towards center.
3. Press seam allowance along upper edge of pocket at 1.5 cm onto wrong side and topstitch. Topstitch pocket onto front according to markings.
4. Sew collar seam, after having pinned fronts right sides together, press seam apart. Sew and press apart shoulder seams, serge. Clip into seam allowance of shoulder seam on front and sew collar into back neckline, press seam apart.
5. Pin sleeves to front and to back wrong sides together and sew so that the seam is on the right side, press seam allowances towards sleeve.
6. Sew side seams and the sleeve seams at the same time, pinning pieces wrong sides together and sewing so that the seam is on the right side. Press seams towards back and topstitch.
7. Sew cuff into a ring. Fold cuff in half lengthwise and press. Sew cuff to sleeve. Press towards sleeve.
8. Cut a rectangle 3x4 cm from self fabric. Pin it under button loop mark and topstitch on the wrong side. Make buttonholes. Sew on buttons.

## TECHNICAL DRAWING:

