

Sewing Pattern — Blouse 4074

Recommendations on fabric: blouse fabric of natural or mixed fibers (silk, viscose).

You will also need: fusing, blind fly zipper, 1 button.


If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: on flounce edges - 2.0 cm, on panel side and top edges, other seams - 1.0 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 2 details.
2. Front part – 2 details.
3. Stand-up part of collar – 2 details.
4. Flounce_1-2 details.
5. Flounce_2 – 2 details.
6. Stand-up collar panel – 1 detail.

INSTRUCTIONS:

1. Serge flounce details on outer sides with thin rolled seam, apply flounce_2 on flounce_1, fix top and middle edges and run as one detail.
2. Sew darts on front panel. Press waist darts towards panel center, breast darts – upwards.
3. Sew darts on back part. Press darts towards middle seam. Sew middle edge of back part. Press seam to the left side and serge.
4. Overstitch front panel neck with flounce. Slash seam allowances near the neck end and serge. Turn flounces onto right side, put together edges of the flounce with middle edge of front part. Sew middle edge of front part, press onto left side and serge.
5. Sew shoulder seams, press allowances onto back part and serge.
6. Serge top and side panel edges with thin rolled seam. Make evenly distributed plaits on the

plane. Fold right sides of stand-up collar details inwards, put the panel between them and overstretch top and side edges starting the seam near the marked allowance of panel inseam. Slash seam allowances near the marking. Turn stand-up part of collar onto right side, straighten seam and press.

7. Sew outer stand-up part of collar into the neckline, turn in the open edge of inner part and topstitch into the sewing seam of outer stand-up part.

8. Cut out (if not available) a bias tape of 4 cm width to run the armhole. Fold bias tape in half lengthwise wrong sides together and press. Fold the bias tape with armhole edge from the right side and overstretch. Turn the bias tape onto wrong side and topstitch along the fold on the main detail.

9. Serge left side edges separately. Sew side seams leaving a slit for zipper in left side seam. Press apart left seam, press right seam towards back part and serge. Sew in zipper into left side seam. Fasten side seam allowance to the armhole with 2-3 stitches.

10. Serge the garment hem, press onto wrong side and topstitch.

11. Serge the buttonhole on right side of stand-up part. Sew a button accordingly.

TECHNICAL DRAWING:

