

Blouse With Waist Inset - Sewing Pattern #2310

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing, 16 buttons.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment – 2 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Upper back – cut 1 on fold
2. Center back – cut 1 on fold
3. Side back – cut 2
4. Upper front – cut 2
5. Center front – cut 2
6. Side front – cut 2
7. Sleeve – cut 2

8. Cuff – cut 2
9. Center front facing – cut 2
10. Back neck facing – cut 1

Fusible interfacing:

1. Cuff – cut 2
2. Center front facing – cut 2
3. Back neck facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side backs to center back, press towards center and serge. Sew upper back to lower part, press towards top and serge.
3. Sew side fronts to front, press towards center and serge. Sew a gathering stitch along the lower edge of upper front and gather fullness. Sew upper front to lower front, press towards top and serge.
4. Sew side and shoulder seams, press seams towards back and serge.
5. Cut a bias tape its length should equal approximately 50 cm and , its width should equal 2.5 cm for loop buttonholes. Fold tape in half lengthwise right sides together and stitch at 0.3 cm from fold. Cut away seam allowances close to seam, turn tape right side out and straighten rolled hem. Cut into 12 parts. Adjust the length of buttonholes. Topstitch button loops onto right front (folds are directed away from the edge).
6. Sew shoulder edges of center front facings and back neckline facing, press seam apart. Serge outer edge. Pin center front facings onto shell right sides together and sew center front edges, front neckline and back neckline. Clip into curves, trim away corners, fold center front facings and neckline facing onto wrong side, straighten, press. Slipstitch to garment along the shoulder seams.
7. Sew a gathering stitch along lower edge of sleeve and gather fullness. Sew sleeve edges separately. Sew sleeve seam from armhole up to mark for slit, press seam apart. Topstitch slit at 0.1 cm from fold. Sew sleeves into armholes, serge and press.
8. Pin cuffs together, right sides together and sew side and lower edges. Start and stop stitching exactly at the marked seam line cuffs. Turn the piece right side out, press. Sew outer side of cuff to sleeve, fold inside the seam allowance of inner cuff and stitch-in-the ditch into seam of outer cuff.
9. Serge hem of garment, press onto wrong side and topstitch.
10. On left front sew on buttons. Make buttonholes and sew on buttons onto cuffs.

TECHNICAL DRAWING:

