

## Sewing Pattern — Dress 4006

Recommendations on fabric: natural / mixed thin costume or dress fabrics; crepe-satin for collar

You will also need: fusing; blind zipper

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams – 1cm; on hem of the dress and hem of sleeve – 2.0 cm, along vent – 6 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

#### Main fabric:

1. Upper back part - 2 details
2. Lower back part - 2 details
3. Upper front part – 1 detail
4. Lower front part - 1 detail
5. Sleeve - 2 details

#### Crepe-satin:

1. Lower collar — 1 detail
2. Upper collar — 1 detail
3. Cowl-neck — 2 details

### **INSTRUCTIONS:**

1. Apply fusing to top collar.
2. Sew darts on details of back part. Press darts to middle seam. Sew top and lower parts of back part. Press seam downwards and serge.
3. Cut off 5 cm on left lower part of back part along vertical edge of the vent. Apply fusing to vent on both details of lower back part from wrong side. Mark middle seam line on right side (vent foldline). Press left part on vent foldline, press only seam allowance of right side of vent (6 cm) on right part onto wrong side. Coincide details on middle seam and fix on top edge of the vent. Serge middle edge of back part separately on each detail. Serge seam allowances of the vent. Sew middle edge of back part up to vent corner. Slash vent seam allowance corner on right part. Press seam allowances of middle seam apart, press vent seam allowances and fix them on right side with machine stitch.
4. Sew darts on details of front part. Press darts towards center of front part. Sew top and lower parts of front part. Press seam downwards and serge.

5. Sew shoulder seams and right side edge, press seam onto back part and serge. Serge left side separately. Sew left side seam from the armhole up to top marker and from lower marker up to hem. Sew in zipper between markers.
6. Fold top and lower collar right sides together and overstretch on fall edge and ledge line. Slash seam near marker «o». Turn collar out and press. Fold cowl-neck details right sides together and overstretch on outer side and ledge. Slash seam near ledge marker, turn crawl-neck collar out and press. Stitch top and lower collar separately to crawl-neck on gorge seam line. Press seams apart. Turn ready collar out and press. Sew outer edge of collar into the neckline, press seam onto collar. Turn open inner edge of collar and topstitch into collar connecting seam. Fix collar and crawl-neck on gorge seam line.
7. Sew edge of sleeve. Press and serge seam. Sew sleeve into armhole, leveling notches and gathering slightly on rounded part. Press and serge seam.
8. Serge seam allowance of the dress hem and hem of sleeve, press onto wrong side and undersew with invisible stitches. It is recommended to wear the dress with the belt.

**TECHNICAL DRAWING:**

