

Sewing Pattern — Dress 4004

Recommendations on fabric: thin fabric suitable for dresses or costumes.

You will also need: invisible zipper, fusing.

If the pattern has double contour, seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance 1 cm on all edges. Hem – 2 cm, sleeve hem – 1.5 cm, vent and upper edge of front part – 6 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.

CUTTING:

Main fabric:

1. Upper back part – 2 details
2. Central back part – 2 details
3. Lower back part – 2 details
4. Upper front part – 1 detail
5. Central front part – 1 detail
6. Lower front part – 1 detail
7. Sleeve – 2 details
8. Back facing – 2 details
9. Belt loop – 1 detail



INSTRUCTIONS:

1. Apply fusing to back neckline facing.
2. Sew darts on upper and lower back parts, press depths to central seam. Sew central back part to upper back part, serge and press downwards. Sew lower back part to central back part, serge and press upwards.
3. Cut off 5 cm on left bottom back part along the vertical edge of vent. Apply fusing to vent on both details of bottom back part from the wrong side. Mark central seam from the right side (vent fold line). Fold left part along the vent fold line and press. Turn vent seam allowance on the right back part to the wrong side (6 cm) and press. Tack the details along central back seam and pin along the upper edge of vent. Serge central back seam on each detail separately. Serge seam allowances on vent. Sew central back seam from zipper marker to vent corner. Slash corner of seam allowance of the vent on right part. Press apart seam allowances of central seam. Press seam allowances of the vent and fasten them with machine stitch from the right side. Sew in zipper.
4. Sew darts on bottom front part. Press darts' depths towards center. Sew central front part to upper front part, serge and press downwards. Sew lower front part to central front part, serge and press upwards.
5. Sew side seams, serge and press onto back piece.
6. Serge outer edges of back neckline facings and seam allowance of upper edge of front part. Overstitch back neckline with facing. Slash seam allowances on rounded areas, turn the facings right side out, press. Fold seam allowance of central edge of facing and fasten to the zipper band.
7. Sew shoulder seams together with back neckline facing and turning seam allowance of outer edge of upper front part onto the shoulder seam. Serge and turn right side out.
8. Serge sleeve hem, fold to the wrong side, press and topstitch. Sew sleeve seam. Serge and press. Sew sleeves into armhole (mind the notches). Serge and press.
9. Serge hem, fold to the wrong side, press and sew with invisible seams.
10. Fold belt loop in half lengthwise right sides together and overstitch - 0.5-0.7 cm off the edge. Turn the right side out and press. Cut loops of required size and topstitch along the markers. Thread in leather belt 2 cm wide.

TECHNICAL DRAWING:

