

Blouse With Decorative Yoke - Sewing Pattern #2412

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 8 decorative beads.

Seam allowances: Seam allowance for hem of garment - 2.5 cm; seam allowance for hem of sleeve - 1.2 cm; other seams - 1.0 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Front yoke - cut 2
3. Front - cut 1 on fold
4. Sleeve - cut 2
5. Stand collar - cut 2
6. Front neck facing - cut 1

Fusible interfacing:

1. Stand collar – cut 1
2. Front neck facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew front darts, press bulk towards top.
3. Serge outer edge of front neckline facing. Pin facing onto front and sew the neckline, clip seam allowances, turn facing under, press.
4. Sew yoke to front (the edge of yoke is longer than the edge of front by the width of seam allowance), press towards top and serge.
5. Sew side and shoulder seams, press seams towards back and serge.
6. Pin stand collars together right sides together and sew outer edges. Start and stop sewing exactly at the marked line of seam. Clip into curves. Turn the finished stand collar right side out and press.
7. Sew outer stand collar into neckline, press seam allowances at stand collar. Turn under the raw edge of inner stand collar and stitch in the ditch.
8. Serge the seam allowances along the lower edge of sleeve, turn inside and topstitch. Sew sleeve seams, press seams towards back and serge. Sew sleeves into armholes, matching notches, serge and press.
9. Turn hem under inside at 1 cm, then at 1.5 cm and topstitch.
10. Sew on decorative beads onto the yoke seam.

TECHNICAL DRAWING:

