

Sewing Pattern — Dress 5981

<u>Recommendations on fabric</u>: knit fabric of medium stretchiness.

You will also need: 3 buttons.

If the pattern has double contour the seam allowances are included. Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: on hem, hem of sleeve and back neckline edge – 1.5 cm, all other seams - 0.8 cm

<u>Attention</u>! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

- 1. Back 2 details
- 2. Front 1 detail
- 3. Sleeve 2 details
- 4. Yoke 2 details
- 5. Collar 1 detail

Advice:

Knitted fabric details are sewn together with special elastic or narrow zig-zag stitch. When serging cut seam allowances to 0.6 - 0.8 cm. Hem is stitched with double needle to save stretchiness. Details also can be sewn together by 3 or 4 – threaded serger.

INSTRUCTIONS:

1. Mark and sew darts on front. Trim depths. Fold collar in half lengthwise wrong sides together and press. Sew collar into the front neckline.

2. Put yokes right sides together and overstitch long straight edge and edge along big semicircle. Trim seam allowances, slash on rounded parts, turn details out and press. Put yoke onto front and attach on edge of the armhole and right shoulder edge. Make pleats on yoke according to marks, inner ridge of pleats is directed upwards to left shoulder edge. Topstitch inner ridge of pleats onto front according to marks that are on details of front. It is recommended to make pleats and topstitch them starting from right side seam.



3. Sew center edge of back. Sew shoulder seams of back and of front (from back side seam allowances of shoulder edge are 1.5 cm longer than front shoulder edge). Press seam allowances towards back and finish them.

4. Sew side seams, finish them and press towards back.

5. On sleeve slit seam allowance from lower corner up to mark «o». Mark and make pleats on sleeve. Depths are directed upwards. Fix pleats along edge. Sew seam from mark «o» up to hem. Finish seam and press it. Sew sleeve seam, finish and press it. Sew sleeve into armhole. Finish and press seam.

6. Serge hem of garment, back neckline and hem of sleeve. Turn onto wrong side, press and topstitch.

7. Sew buttons on yoke and on sleeves according to marks.

TECHNICAL DRAWING:

