

Sewing Pattern — Dress 5944

Recommendations on fabric: natural or mixed fabric suitable for dresses.

You will also need: invisible zipper, fusible interfacing.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance : all seams 1 cm, hem of the garment and lower edge of sleeve - 3 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Central back - 2 details
2. Middle part of back - 2 details
3. Side back - 2 details
4. Side front - 2 details
5. Middle part of front – 2 details
6. Central front – 1 detail
7. Sleeve - 2 details
8. Inset - 2 details
9. Back facing_1 – 2 details
10. Back facing_2 – 2 details
11. Front facing – 2 details

Interfacing:

1. Back facing _1 – 2 details
2. Back facing _2 – 2 details
3. Front facing – 2 details

INSTRUCTIONS:

1. Apply interfacing to corresponding details as well as to one-piece seam allowance of top edge of front.

2. Sew side and middle parts of back, press seam allowances to middle part and serge. Sew side and middle parts of front, press seam allowances to middle part and serge. Sew side seams, press seam onto back and serge.
3. Serge lower edge of inset, press onto wrong side and undersew with invisible stitches. Make pleats according to marks. Stitch inset to dress, press seam allowances upwards and serge.
4. Serge center edge of back. Sew center edge of back from top edge up to top notch, from lower notch down to hem, press seam allowances apart. Sew in zipper. Serge lower edge. Also serge lower edge of central front.
5. Sew central and middle parts of back, turning hem seam allowance of central part onto the right side and enveloping middle part, press seam allowances toward center and serge. Turn and straighten lower corner. Sew central and middle parts of front from notch of top edge down, turning seam allowance of central part's hem onto right side and enveloping middle part. Slash seam allowances near top notch, press toward center and serge. Turn out and straighten lower corner.
6. Sew together back facing 1 and back facing 2, press seam allowances apart. Sew center edge of back facing, press seam allowances apart. Sew shoulder seams of the back and front facings, press seam allowances apart.
7. Place the facing and garment right sides together and overstretch the neckline of back and of front from notch up to marker, slash seam allowances on rounded parts. Sew one-piece facing of central front and lower section of front facing, press apart seam allowances on this section. Serge round outer edge of the facings. Turn the facing wrong side out, straighten, press. Fasten the facing to seams with several stitches.
8. Sew edge of sleeve, press seam onto elbow part and serge. Sew sleeve into the armhole according to notches, press and serge seam allowances.
9. Serge lower edge of sleeve, press onto wrong side and undersew with invisible stitches. Also undersew unsewn sections of main garment hem.

TECHNICAL DRAWING:

