

Sewing Pattern — Coat 5916

Recommendations on fabric: soft woolen fabrics, cashmere

You will also need: fusible interfacing; lining; raglan shoulder pads (for blouses); 7 buttons of 2.5 – 3.5 cm diameter; 8 buttons of 1 – 1.3 cm diameter; clasper of 5 cm wide

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowances: all seams - 1 cm, hem of the garment and hem of sleeve - 3.5 cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric:

1. Back yoke – cut 2
2. Front yoke – cut 2
3. Side back – cut 2
4. Center back – cut 2
5. Lower back – cut 2
6. Side front – cut 2
7. Center front – cut 2
8. Collar-stand – cut 2
9. Collar – cut 2
10. Outer collar – cut 2
11. Back neck facing – cut 1
12. Front band facing – cut 2
13. Belt – cut 1
14. Front section of pocket – cut 2
15. Side section of pocket – cut 2

16. Pocket frame – cut 2
17. Basque – cut 1 on fold
18. Belt loop – cut 1

Lining:

1. Back yoke – cut 2
2. Front yoke – cut 2
3. Side back – cut 2
4. Center back – cut 2
5. Lower back – cut 2
6. Side front – cut 2
7. Center front – cut 2
8. Basque – cut 1 on fold
9. Pocket – cut 2

Fusible interfacing:

1. Front band facing – cut 2
2. Back neck facing – cut 1
3. Collar – cut 1
4. Collar-stand – cut 1
5. Outer collar – cut 1

ATTENTION: Front and back lining pieces are cut according to main fabric patterns excluding the width of front band facings and back neck facing, correspondingly.

Note: serge princess seams and side seams of main fabric and lining details from hem up to waist.

INSTRUCTIONS:

1. Apply fusible interfacing to front band facings, back neck facing, and collars. Apply fusible interfacing to armhole on side front. Sew grain selvage of 1 cm wide along top edge of sleeve from neckline down to hem of sleeve on details of front and of back. Apply interfacing to corners on armhole and on neckline of front and back yokes.
2. Sew side backs to center backs, press seams apart. Sew center back seam. Press seams apart. Sew center seam of back yokes together, press seam apart. Slash corner on back yoke near the beginning of the armhole. Sew back yoke to back. Press seam apart. Sew sections of lower part of the armhole and rounded part on back. Press seam to the sleeve.
3. Pin basque with basque lining right sides together and sew along the lower edge. Turn right side out, press. Topstitch seam allowances along the lower edge onto lining. Then sew the basque as one-layer detail. Make pleats along top edge of the basque. Inner ridges of the pleats are directed toward center of the back. Fix pleats along top edge.
4. Sew darts on lower back. Press darts toward center. Sew center seam of lower back. Press seam apart and serge. Fix basque to lower back along top and side edges. Sew top and lower back. Press seam upwards.
5. Sew side fronts to center fronts. Press princess seam apart. Slash corner on front yoke near beginning of the armhole. Sew yoke to the front. Press seam apart. Sew sections of lower part of the armhole and rounded part on the front. Press seam to the armhole.
6. Pocket: Sew bospal and side section of the pocket. Press seam towards side section. Shape a bospal of 1 cm wide. Align bospal foldline to center line (marked on the pattern). Press the bospal. Put a fixing stitch along connecting seam of the bospal to side section. In the same way, sew front section of pocket. Pin pocket to lining right sides together and sew all edges, except the side edge. Turn right side out and press. Sew on buttons. Button marking is on the pattern of lining pocket. Topstitch the pocket according to markers. Topstitch only front and lower sides of the pocket. Side

edge is not topstitched.

7. Sew top edges of sleeves. Press seams apart. Sew lower sleeve seam and side seam with one continuous stitch. Press seams apart and serge.

8. Pin collar right sides together and sew outer edges. Clip into curves, turn collar out and press. Pin collar-stand right sides together, insert collar between them. Sew only upper edge of the collar-stand. Turn right side out and press. Pin outer collar right sides together and sew. Turn collar out and press. Fix outer collar to collar-stand along the lower edge. Trim corner on front neckline. Sew collar into the neckline. Sew ends of collar-stand into the front neckline. Clip into curves and press towards front and back side.

9. Sew shoulder seams of back neck facing and front band facings. Press seams apart. Trim corner on front band neckline.

10. Pin facing to the front, right sides together, and sew center front and neckline. Understitch. Sew lower edge of the front band facing to the front exactly on hem marked line, leaving 1.5 cm to inner edge of the facing. Trim lower corner seam. Turn facing onto right side, straighten seams. Press collar and facing.

11. Serge belt loop along one side (long side). Turn unsewn edge inside, and close with the serged one. Sew two parallel stitches at 0.1 cm from the edge. Cut belt loops. Stitch belt loops to side edge.

12. Sew lining pieces the same way as main fabric pieces. Turn seam allowance of lower edge of lining twice at 1.5 cm and topstitch.

13. Serge and press hem seam allowance of the garment. Sew in shoulder pads. Sew lining to inner edges of facing. Start and finish the stitch on half width of main garment hem turnup. Trim seam allowance on inner edge of the front band facing near the start of lining connection. Turn seam allowance of facing inside from hem line to the slash and sew with invisible stitches. Serge the seam of lining and press towards side of lining.

14. Sew lining to hem of sleeve. Press seam onto lining.

15. Make buttonholes on the right front, sew buttons on left front. Sew buttons through according to markers on the collar.

16. Fold the belt in half lengthwise, right sides together, and sew on long and one short sides. Turn belt right side out, turn seam allowances of unsewn section inside, and make a decorative stitch at 0.7 cm along the perimeter of the belt. Insert and fasten the clasper to the belt.

TECHNICAL DRAWING:

