

Sewing Pattern — Tunic 5913

Recommendations on fabric: natural/mixed light-weight wool

You will also need: fusible interfacing, 7 buttons, pocket lining

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance: hem of the garment – 2 cm, small and big pocket bags edges - 2 cm, off-set welt edges – 2 cm, other seams – 1cm

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Main fabric:

1. Front - cut 1
2. Back - cut 1
3. Sleeve – cut 2
4. Left front yoke – cut 2
5. Right front yoke – cut 2
6. Outer button placket – cut 1
7. Inner button placket – cut 1
8. Cuff – cut 2
9. Back yoke - cut 2
10. Sleeve placket – cut 2
11. Off-set pocket welt – cut 2
12. Big pocket bag – cut 2

Lining:

1. Small pocket bag – cut 2

Interfacing:

1. Outer placket – cut 1
2. Inner placket – cut 1
4. Cuff – cut 2
5. Off-set welt – 2 details

INSTRUCTIONS:

1. Apply interfacing to plackets, cuffs, off-set welt.
2. Sew darts on front and press toward hem. Mark and make pleats. Baste them along upper edge.
3. Sew front yokes to front. Serge seams and press onto yoke.
4. Fold off-set welt in half lengthwise, right side out, press. Apply interfacing to pocket-opening edges. Mark a line on off-set welt that determines the width of off-set welt when ready. Topstitch small pocket bag to inner side of off-set welt. Lay off-set welt on right side of the front along lower marked line, right side downwards, aligning marked line of pocket and line on off-set welt. Sew off-set welt. Sew big pocket bag to upper mark of pocket. Cut pocket opening in the center between marks, making cross slashes to corners of pocket marks. Turn details of pocket onto wrong side. Straighten seam allowances and press. Sew edges of pocket bags, fixing corners of pocket.
5. Sew yoke to back. Serge and press onto yoke.
6. Sew shoulder and side seams. Serge seams and press toward back.
7. Sew upper corners of plackets, right sides together. Turn right side out and press. On the front, cut between lines of placket marks, making cross slashes to corners at marks. Pin plackets outer side to right side of front, matching edges. Sew plackets to front. Turn plackets onto right side. Place lower edges of plackets inside. Sew across plackets on bottom edges. Sew shoulder seams of inner yokes. Press seam allowances apart. Serge outer edges of the yoke. Pin inner yokes to main garment, right sides together, and sew edges of plackets and neckline, turning upper corners of plackets away so that they do not get caught in the seam. Clip into curves. Turn garment onto right side and topstitch inner yoke into connecting seam of outer yoke.
8. Sewing the sleeve vent: cut sleeve along marked line, slashing corner in upper part of the slit. Turn section of 1. 7 cm from the slit up to marked line twice inside at 0. 5 cm and topstitch. Fold placket in half lengthwise, right sides together, and sew the corner up to cross marker. Trim seam allowances off close to the stitch, snip seam allowance near the end of the stitch. Turn placket out, press and sew along fold-line from below up to cross marker at 0,1 cm. Pin placket to the sleeve, right sides together, and sew with inner side along marked line. Snip sleeve near end of the stitch, crosswise from the slit up to connecting line. Turn the placket onto right side, turn open edge and sew. Align placket to marked line on the sleeve and topstitch top corner along contour and along cross marker.
9. Sew sleeve seam, serge and press. Make a gathering stitch along edge of sleeve and gather fullness. Fold cuffs, right sides together, and sew short sides. Turn cuffs right sides out, and press. Sew outer side of cuff to the sleeve. Turn under inner-side of cuff and topstitch into connecting seam.
10. Make a gathering stitch along sleeve cap for ease. Sew in the sleeve, easing along sleeve cap.
11. Serge the bottom edge of garment. Turn hem of the garment twice onto wrong side and topstitch.
12. Make buttonholes on cuffs and sew buttons. Make buttonholes on outer placket, sew buttons on inner placket.

TECHNICAL DRAWING:

