

Sewing Pattern — Jacket 5870

<u>Recommendations on fabric:</u> natural/mixed thick fabrics, e.g. denim

You will also need: fusing, 6 buttons.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: on hem of the garment – 3 cm, all other seams – 1cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

- 1. Back part 1 detail
- 2. Back yoke 1 detail
- 3. Front part yoke 2 details
- 4. Central front part 2 details
- 5. Side front part 2 details
- 6. Sleeve 2 details
- 7. Collar 2 details
- 8. Cuff 2 details
- 9. Off-set welt 2 details
- 10. Lining of pocket 4 details

Fusing:

- 1. Collar 1 detail
- 2. Cuff 2 details
- 3. Off-set welt 2 details
- 4. One-piece panel yokes of front part and central front part



INSTRUCTIONS:

- 1. Apply fusing to one-piece panels of front part and central front part yokes, to collar, off-set welts and cuffs.
- 2. Fold top collar with lower collar right sides together. Overstitch ends and outer edge of collar, starting and finishing the stitch exactly near marked line of collar connecting seam. Cut seams, turn out, straighten and press collar.
- 3. Fold off-set welt in half lengthwise right sides together and overstitch on short sides. Cut seam allowances in corners, turn off-set welt onto right side and press. Put decorative stitch along short and one long sides. Stitch one of the pocket linings to off-set welt.
- 4. Put lining of pocket onto right side of side front part, and pocket lining with stitched off-set welt onto central part front part according notches right side downwards. Stitch lining of pocket to seam allowance of pocket opening. Serge relieve edges of front part together with vent seam allowances.
- 5. Sew relieves of front part together with lining of pocket up to the vent. Press seam allowances towards center. Sew linings of pocket and serge. Put decorative stitch along relieve seam on right side at 0. 2 cm. Topstitch short sides of off-set welt onto side part of front part.
- 6. Press vent seam allowance of side front part in half. Fold vents so that central part vent is from above and put fixing stitch on vent ground.
- 7. Make a counter plait on back part. Stitch yoke of back part to back part, press seam onto yoke and topstitch on 0. 2 cm off the seam. Stitch yoke of front part to front part, press seam onto yoke and topstitch on 0. 2 cm off the seam.
- 8. Serge edge of one-piece panel, turn it onto right side of front part and overstitch top corner from fold up to center line, overstitch lower corner exactly on marked hem line. Slash seam allowances in corners. Turn the panel out, press and topstitch onto front part, catching inner edge of pocket lining.
- 9. Sew shoulder and side edges, press seam allowances apart and serge.
- 10. Sew lower collar into the neckline of the jacket. Turn seam allowance of top collar inside and topstitch into lower collar connecting seam.
- 11. Fold cuffs right sides together and overstitch short edges and transitive end.
- 12. Serge edges of sleeve, sew up to marker slit, press apart, pressing the slit. Put decorative stitch on slit edge. Stitch top cuff to lower edge of sleeve. Turn upper edge of lower cuff inside on 1 cm and topstitch into top cuff connecting seam. Put decorative stitch along cuff contour.
- 13. Sew sleeve into the armhole, press seam allowances.
- 14. Serge hem of garment. Overstitch lower corners of vents, put the stitch exactly on marked hem line. Topstitch seam allowance onto jacket along serge line.
- 15. Put decorative stitch on 0. 2 cm off the edge along buttonstand and collar line.
- 16. Serge buttonholes on right front part, sew buttons on left front part. Make buttonholes and sew buttons on cuffs.



TECHNICAL DRAWING:

