

Sewing Pattern — Bolero 5853

Recommendations on fabric: dress fabrics of natural or mixed fibers.

You will also need: piping with pencil edge

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm, along the edge of sleeve – 3 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Front part – 2 details
2. Back part – 2 details
3. Buttonstand – 2 details
4. Back neckline facing – 1 detail
5. Bottom facing of back part – 1 details
6. Sleeve – 2 details

INSTRUCTIONS:

1. Sew shoulder darts onto back part, press depths towards center. Sew middle edge of back part, press on left side and serge.
2. Sew shoulder seams, slashing in corners. Serge and press towards back part.
3. Sew middle edge of collar on front part details, press seam allowances apart. Sew lower collar in the neckline of back part. Slash connection seam and press apart.
4. Sew side seams. Serge and press towards back part.
5. Sew middle edge of collar on buttonstand details, press seam allowances apart. Sew shoulder seams of buttonstands and back part neckline facings, slashing in corners. Sew top collar in the neckline facings. Press connection seam apart. Stitch t back part hem facing to buttonstands, press seam allowances apart. Serge inner edges of buttonstands and facings of the neckline and hem of back part.

6. Topstitch piping onto bolero on stands, lower edge of back part, lapels and outer edge of collar.
7. Fold bolero and buttonstands right sides together and overstitch roundwise. Slash seam allowances on rounded parts, turn bolero onto right side, straighten and press seams.
8. Sew edges of sleeve. Serge and press onto back part. Sew sleeves into armholes according to notches. Press seam allowances and serge.
9. Serge hem of sleeve. Turn seam allowance inside and undersew with invisible stitches.

TECHNICAL DRAWING:

