

Sewing Pattern — Lingerie 5792

Recommendations on fabric: silk, well-draping fabric suitable for lingerie.

You will also need: bias tape in contrasting color (the approximate length is mentioned on back pattern), elastic for waistline.

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam allowance 1 cm on all edges. Sleeve hem and neckline of front and back – 0 cm.

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Fabric:

1. Lower back – cut 1
2. Back sleeve – cut 2
3. Front sleeve – cut 2
4. Lower front– cut 2

INSTRUCTIONS:

1. Fold bias tape in half lengthwise, wrong sides together, press, and sew to back neckline.
2. Sew upper sleeve seam, serge and press onto front. Fold bias tape in half lengthwise, wrong sides together, press, and sew to sleeve hem.
3. Serge front edge, press onto wrong side, and topstitch.
4. Sew lower front to front sleeve, ending stitch exactly at the seam allowance for side seam. Clip seam allowance near end of stitch, serge and press upwards. Fold bias tape in half lengthwise, wrong sides together, press, and sew to front neckline, at the same time making ties for neckline and the tie on right front.
5. Sew lower back to back sleeve, ending stitch exactly at the seam allowance for side seam. Clip seam allowance near end of stitch, serge and press upwards.
6. Make a tie 40 cm from the bias tape. Sew sleeve seam and side seam, inserting the tie into left side seam. Serge the seam and press.
7. Serge lower edge of garment, press onto wrong side, and topstitch.
8. Topstitch elastic along seam connecting upper and lower front and back. The elastic equals waist girth + 12 cm, so you will need to stretch it equally along the seam while stitching (It helps to pin it at equal distances along the seam and then stretch gently between pins).

TECHNICAL DRAWING: