

## Sewing Pattern — Blouse 5751

Recommendations on fabric: soft sheer fabric.

You will also need: piping; bride; 1 button .

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 2 cm for the hem, 0 cm for neckline edge, 1 cm for other seams.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

Fabric:

1. Back part – 2 pieces
2. Front part – 1 piece
3. Front yoke – 1 piece
4. Back yoke – 2 pieces
5. Sleeve – 2 pieces

### **INSTRUCTIONS:**

1. Stitch waist front/back darts. Press darts toward center.
2. Stitch shoulder darts into back yoke. Press darts toward back middle seam.
3. Make pleats into front neckline as marked. Make fixing stitch at 0.5 cm from neckline edge.
4. Stitch shoulder edges into front/back yokes. Neaten the seam and press it backward.
5. Stitch sleeves to back/front parts along armhole lines. Neaten seams and press them toward sleeves. Make a seam with loose stitches along sleeve upper edge and gather fabric a little.
6. Stitch yokes to front/back parts and to sleeves. Neaten seams and press them upward.

7. Mark bride line on sleeves. Lay the sleeve wrong side up, stretch the bride and topstitch it with zig zags leaving 1 cm ends.
8. Stitch sleeve/side edges with one stitch. Neaten seams and press them backward.
9. Stitch back middle edge between closure mark and the hem. Press seams apart and neaten them.
10. Overstitch the neckline with the piping forming a closure loop on back side. Sew a button to another side of closure.
11. Process sleeve hems. Neaten blouse hem. Fold it under and topstitch.

**TECHNICAL DRAWING:**

