

Sewing Pattern — Dress 5686

Recommendations on fabric: natural/mixed fabric

You will also need: concealed zip.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams, 2 cm for the hem

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 2 pieces
2. Left front part – 1 piece
3. Right front part – 1 piece
4. Back skirt – 2 pieces
5. Front skirt – 1 piece

INSTRUCTIONS:

1. Neaten left/right front parts' upper edges. Press upper edges into wrong side, then stitch.
2. Make pleats in right front part. Lay right front part on left one and fix them together along lower/side edges.
3. Stitch dress side edges, press seams backward and neaten them.
4. Stitch skirt side edges. Press seams backward and neaten them.
5. Make loose stitches along lower skirts' upper edges. Pull the edge to make it equal to dress upper parts' lower edges, adjust pleats evenly. Stitch dress upper parts to skirts. Press the seam

upward and neaten it.

6. Neaten middle back edges. Stitch middle back seam between the mark and the hem. Press the seam apart pressing closure slit's allowance.

7. Stitch the zipper under slit allowances with its teeth invisible.

8. Mark armhole line on front part. Make loose stitches along this line. Pull the edge to necessary length.

9. Cut 2 pipings of 4 cm width and of length equal to which is marked on patterns. Press pipings along the center right side out. Then fold them flat and press long edges to marked center. Cut seam allowances on back décolleté and front armholes and trim this edge with the piping making shoulder straps in the same time.

10. Try the dress on, adjust straps length and fix them on back part.

11. Press the hem into wrong side, fold it under and topstitch.

TECHNICAL DRAWING:

