

Sewing Pattern — Blouse 5684

Recommendations on fabric: silk or fabric with artificial fibers.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams, 2 cm for hem.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Back part – 1 piece
2. Front part – 1 piece
3. Back facing – 1 piece
4. Front facing – 1 piece

INSTRUCTIONS:

1. Stitch shoulder edges. Press shoulder seam apart and neaten them.
2. Apply the fusing to wrong side of front/front facing slit. Stitch front/back facings' shoulder edges. Press shoulder seam apart. Lay the facing on the garment right sides together, then overstitch the neckline as well as along the slit; do not stitch a segment at mark level. The seam at slit top is 0.5 cm, the seam at slit bottom is 0.2 cm. Cut the slit. Fold the facing into wrong side and press it folding under facings at unstitched segment.
3. Stitch blouse side edges. Press side seams backward and neaten them.
4. Cut 8 ties of necessary length and of 4 cm width. Press ties along the center right side out. Then lay them flat and press long edges to marked center line. Fold ties along middle line coinciding bendings, then topstitch at 0.1 cm.
5. Make loose stitches along neckline as marked. Pull stitches to necessary length and fix them. Set ties into unstitched segments of front slit and fix them with machine stitches.
6. Cut a piping of 4 cm width and of length equal to armhole length. Press the piping along the center

right side out. Lay the piping on the armhole right sides together and overstretch. Fold the piping into wrong side. Topstitch seam allowance on the piping with 0.1 cm width seam. Topstitch piping's bending on the armhole.

7. Neaten the hem, fold it into wrong side and topstitch.

TECHNICAL DRAWING:

