

Sewing Pattern — Jacket 5610

Recommendations on fabric: wool/semi-wool

You will also need: fusing, separating zip (see zip length on front part's pattern), lining, shoulder pads.

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

SEAM ALLOWANCE: 1 cm for all seams, 3 cm for garment/sleeve hems.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Center back part – 2 pieces
2. Side back part – 2 pieces
3. Front part – 2 pieces
4. Side front part – 2 pieces
5. Back neckline facing – 1 piece
6. Front band – 2 pieces
7. Upper sleeve – 2 pieces
8. Lower sleeve – 2 pieces
9. Outer collar – 1 piece
10. Inner collar – 1 piece
11. Off-set welt – 2 pieces

Lining:

1. Center back part – 2 pieces
2. Side back part – 2 pieces
3. Front part – 2 pieces (excluding front band width)
4. Side front part – 2 pieces
5. Upper sleeve – 2 pieces
6. Lower sleeve – 2 pieces
7. Pocket – 4 pieces

Fusing: front band, back neckline facing, outer collar, off-set welt.

INSTRUCTIONS:

1. Apply the fusing to wrong side of front band, back neckline facing, outer collar, off-set welt.
2. Fold the welt along the center wrong side out, then overstitch ends. Cut allowances in corners and turn the detail right side out. Press off-set welt. Stitch pocket lining to the welt.
3. Neaten front relieves at pocket entrance segment. Lay the sacking on side front part's right side. Lay the sacking with off-set welt on center front part, right sides together, according to notches. Stitch the sacking to pocket entrance allowance. Fold the sacking sidewise and topstitch the allowance at 0.2 cm from the seam.
4. Stitch front relieves up to the notch. Stitch the sacking. Press relieve allowances toward center and press the sacking. Neaten the sacking. Topstitch off-set welt's short edges on side front part.
5. Stitch back middle seam and press it apart. Stitch back relieves and press them apart.
6. Lay front parts right sides together, make edges equal measuring front edgings' length. Stitch the zipper to front edgings. Press front edging under at zipper segment.
7. Lay collars together and overstitch along the contour. Slash corners and turn them right side out. Press the collar.
8. Pin front band to front part right sides together and overstitch along front edgings. (Overstitching goes upwards on front part's side.) Stitch front bands' hems to center front part along hem allowance line. Cut front edging's lower corners' seams. Turn front edgings right side out and press seams.
9. Stitch side/shoulder seams and press them apart.
10. Stitch shoulder edges of back neckline facing/front bands and neaten them. Overstitch back/front neckline. Fold facing into wrong side, press seams.
11. Stitch elbow seam and press it apart. Press sleeve hems under. Stitch sleeve front seam and press it apart.
12. Stitch sleeve into armholes according to notches. Stitch shoulder pads in.
13. Stitch lining details together and stitch sleeves in leaving a hole into sleeve's front right seam.
14. Stitch the lining to inner edges of front bands/back neckline facing. Fix allowances of collar/facing neckline together.
15. Stitch the lining to jacket/sleeve hems. Turn the jacket right side out though the hole in the sleeve. Stitch hole's edgestogether.
16. Make decorative stitch along the zipper at 0.5 cm distance.

TECHNICAL DRAWING:

