

Sewing Pattern — Blouse 4222

Recommendations on fabric: silk stretch-atlas

You will also need: fusing, 2 hooks with eyelets

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm, lower edge of back and front parts and of fly panel – 2 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Back part - 2 details
2. Front part - 2 details
3. Fly panel - 2 details
4. Stand-up part of collar - 4 details
5. Sleeve – 2 details
6. Cuff – 2 details
7. Front neckline facing – 1 detail

Fusing:

1. Cuff – 2 details
2. Stand-up part of collar - 4 details
3. Front neckline facing – 1 detail

INSTRUCTIONS:

1. Apply fusing to details .
2. Sew shoulder, waist and bust darts on details of back part and of front part. Press depths of waist and shoulder darts towards center of the detail, depths of bust darts - upwards.
3. Serge separately center edges of back part. Sew center seam of back part from marker up to lower edge, press seam allowances apart, pressing the slit.
4. Fold stand-up parts details pairwise and overstitch top and middle edges, inserting hooks and eyelets. Start and finish the stitch exactly near marked line of neckline connecting line. Sew outer

stand-up part of collar into the back part neckline, turn inner stand-up part of collar and topstitch into connecting seam.

5. Make and fasten pleats on the front, depths are directed upwards. Sew center edge of front part, press seam onto left side and serge.

6. Fold details of fly panel right sides together and overstretch side edges. Turn detail onto right side, press. Put fly panel part onto front part, make free pleats along top edge and fix to front part along the lower edge and neckline edge.

7. Serge outer edge of front part facing. Fold the facing with front part right sides together and overstretch neckline edge, slash seam allowances on rounded parts.

8. Sew side seams. Press seam allowances to back part and serge.

9. Sew shoulder seams, inserting back part between front part and facing. Serge seam allowances, turn facings onto wrong side and press.

10. Cut bias tape to pipe the slit of sleeve 18*3 cm in cut. Mark closure line on the sleeve, cut the sleeve along the line. Lay the sleeve on slit line into straight line and overstretch the slit with piping seam with closed edge. Width of the piping is 0.5 – 0.7 cm. The width of the seam on slit length is 0.5 – 0.7 cm, in top part of the slit it reduces to 0.2 cm. Sew and serge edges of sleeves. Make pleats according to markers.

11. Fold cuff in half lengthwise right sides together and sew side edges and overstretch the corner. Start and finish the stitch exactly near marked line of cuff connecting seam. Slash seam allowances near the marker. Turn detail onto right side, press. Stitch outer side of cuff to the sleeve, turn seam allowance of inner side of cuff inside and topstitch into outer cuff connecting seam.

12. Stitch loosely along top part of rounded part and gather ruffles. Sew sleeve into armhole, leveling notches. Serge seam allowances and press them to sleeve.

13. Make buttonholes and sew buttons on cuffs.

14. Serge lower edge, press onto wrong side and topstitch. **ADVICE:** Wear the blouse with the belt.

TECHNICAL DRAWING:

