

Sewing Pattern — Dress with Patch Pocket 5464

Recommendations on fabric: sheer fabric.

You will also need: decorative cord.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Pocket – 1 piece
2. Pocket side – 1 piece
3. Coulisse – 1 piece
4. Pocket side_2 – 1 piece
5. Pocket_2 – 1 piece
6. Front yoke – 1 piece
7. Front part – 1 piece
8. Back part – 2 pieces

INSTRUCTIONS:

1. Sew yoke to front part; neaten joining seam and make decorative stitch at 0.5 cm from joining seam.
2. Mark place of pockets at front/back parts. Neaten outer edge of pocket side and press at 1 cm. Sew pocket side to pocket. Neaten joining seam. Neaten lower/upper edges of pocket and pocket entrance edge. Press pocket entrance allowance to wrong side and topstitch. Press upper/lower edges of pocket at 1 cm. Lay the pocket on marking. Topstitch pocket sides at 0.2 cm from edges; stop stitching 2-2.5 cm before end. Topstitch pocket upper side at 0.2 cm from edge fixing pocket edges with 2-2.5 cm length stitches. Topstitch pocket lower side at 0.2 cm from edge fixing pocket edges with 2-2.5 cm length stitches and stitching a slit in seam.
3. Sew pocket side_2 to pocket_2 and neaten joining seam. Neaten pocket upper edge and topstitch it at 0.5 cm from pocket edge.
4. Neaten side edges of front/back parts. Sew garment right side seam and topstitch pocket_2 along marking.

5. Neaten back middle edges, then sew them together and press apart. Press coulisses side edges at 1 cm and make decorative stitch along short edges at 0.5 cm from edge. Mark coulisse place and topstitch along long sides at 0.2 cm from edge.
6. Sew garment left side seam up to notch and press the seam apart pressing slits. Make decorative stitch along the slit at 0.5 cm from edge.
7. Fold the piping along the center and overstitch front/back neckline edge and armhole edges with the piping.
8. Sew garment shoulder seams. Neaten seams and press backwards.
9. Neaten the hem, press to wrong side and topstitch. Pull the cord into coulisse.

TECHNICAL DRAWING:

