

Jacket With Buttons - Sewing Pattern #2057

Recommendations on fabric: natural/mixed fabrics suitable for outdoor jackets.

You will also need: lining; fusible interfacing; decorative cord; 2 cord stops; 2 eyelets; 2 grommets; 6 buttons.

Seam allowances: all seams 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back — cut 1 on fold
2. Front – cut 2
3. Stand collar – cut 2
4. Sleeve – cut 2
5. Back neck facing – cut 1
6. Center front facing – cut 2
7. Lower placket – cut 1

8. Cuff – cut 2
9. Flap – cut 4

Lining:

1. Back – cut 1 on fold
2. Front – cut 2
3. Sleeve – cut 2
4. Large pocket bag – cut 2
5. Small pocket bag – cut 2

Fusible interfacing:

1. Center front facing – cut 2
2. Back neck facing – cut 1
3. Stand collar - cut 1
4. Flap – cut 2
5. Placket center front facings – cut 2
6. Cuff – cut 2

Lining is cut using pattern blocks for Shell except for the width of back neckline facing and center front facing.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Pin together flaps right sides together and sew along side and lower edges. Trim seam allowances, turn the flap right side out and press. Sew a decorative stitch along side and lower edges at 0.2 – 0.5 cm from the edge. Sew flap to front along upper line of the pocket marking(the finished edge is directed towards neckline). Sew large pocket bag to front along upper marked line of pocket. Sew smaller pocket bag to front along the lower marking of the pocket. Stop stitching near short marking lines of the pocket. Slash through pocket opening. Snip diagonally toward end of stitching at 1-1.5 cm from end of pocket opening. Turn flaps and pocket bags onto wrong side through the resulting opening. Sew a double back stitch lines near corners to fix ends of pockets. Sew together edges of pocket bags.
3. Sew shoulder and side seams. Press the seam apart.
4. Sew sleeve seam. Press the seam apart. Sew sleeves into armholes matching notches. Press seam.
5. Install grommets on lower placket. Pin lower placket onto front and onto back from the right side and sew along lower edge. Fold placket onto wrong side and press.
6. Sew shoulder seams of central front facings and facings. Press the seam apart.
7. Sew seams on lining.

8. Sew lining to the central front facings and to facing. Sew lower edge of lining to upper edge of placket. Sew a fixing stitch on the right side, making a casing. Baste lining to seam allowance of hem of sleeve. Turn onto right side through the center front edge. Baste shell and center front facing together along neckline and center front edge, treat as one piece in the future.
9. Fold the center front placket in half lengthwise, right sides together and sew lower edge. Start and stop stitching exactly at the marked line of the placket seam. Trim away corners, turn right side out and press. Sew outer edge of placket to front, press the seam allowance at placket. Fold under the seam allowance of the inner side inside at 1 cm and topstitch into seam of. Sew a decorative stitch along the outer edge of placket at 0.2 - 0.5 cm from the edge.
10. Pin stand collars together right sides together and sew along the upper edge. Clip into curves, turn right side out and press. Sew outer stand collar into neckline, press the seam allowance at stand collar. Fold under the seam allowance of the inner side inside at 1 cm and topstitch into seam of.
11. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise and press. Sew outer side of cuff to sleeve, press towards cuff. Fold under the seam allowance of the inner side inside at 1 cm and topstitch into seam of.
12. Thread in the cord, install cord stops and eyelets.
13. Make buttonholes, sew on buttons. Make buttonholes on flaps, sew on buttons onto pockets.

TECHNICAL DRAWING:

