

Dress With Asymmetrical Closure - Sewing Pattern #2072

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 6 buttons.

Seam allowances: all seams 1 cm; seam allowance for hem of garment – 2 cm; seam allowance for hem of sleeve – 1.2 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Right Center front – cut 1
3. Left Center front – cut 1
4. Right Side front – cut 1
5. Left Side front – cut 1
6. Lower front - cut 1
7. Placket - cut 1

- 8. Sleeve - cut 2
- 9. Back neck facing - cut 1
- 10. Right Front neck facing - cut 1
- 11. Left center front facing - cut 1

Fusible interfacing:

- 1. Placket - cut 1
- 2. Back neck facing - cut 1
- 3. Front neck facing right - cut 1
- 4. Left center front facing - cut 1

INSTRUCTIONS:

- 1. Apply fusible interfacing.
- 2. Sew darts on back, press the inner part towards center.
- 3. Sew princess seams on left and right front (sew side part to center part), press towards center and serge.
- 4. Sew shoulder seams, press towards the back and serge.
- 5. Sew right front neckline facing and center front facing to back neckline facing, press the seam apart. Serge the outer edge. Pin center front facing and facings onto Shell right sides together and sew neckline and left center front edge. Clip into curves, trim away corner.
- 6. Fold placket in half lengthwise right sides together and sew upper corner. Turn the piece right side out, straighten, press. Sew outer part to right front, turn under seam allowance of inner part and topstitch into seam of.
- 7. Put right front onto left front and baste together along lower edge.
- 8. Make a box pleat on lower front. Sew upper front to lower front, press seam allowance towards bottom and serge.
- 9. Sew side seams, press towards the back and serge.
- 10. Serge seam allowance along lower edge of sleeve, press onto wrong side and topstitch. Sew sleeve seam, press towards the back and serge. Sew sleeves into armholes matching notches and adjusting ease, serge and press.
- 11. Serge bottom edge of garment, press onto wrong side and topstitch.
- 12. Make buttonholes on placket. Sew on buttons onto left front.

TECHNICAL DRAWING:

