

## Jacket With Decorative Front - Sewing Pattern #4423

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: lining; fusible interfacing; 6 buttons; shoulder pads, brooch.

Seam allowances: Seam allowance for hem of garment and seam allowance for hem of sleeve — 3 cm, other seam allowances 1 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Center right front - cut 1
4. Side front - cut 2
5. Center left front — cut 1
6. Stand collar - cut 2
7. Upper sleeve - cut 2

8. Lower sleeve - cut 2
9. Back neck facing - cut 1
10. Center front facing of right front - cut 1
11. Center front facing of left front — cut 1

Lining:

1. Center back - cut 2
2. Lining of right front - cut 1
3. Lining of left front - cut 1
4. Side back - cut 2
5. Side front - cut 2
6. Upper sleeve - cut 2
7. Lower sleeve - cut 2
8. Pocket bag — cut 4

Fusible interfacing:

1. Center front facing of right front - cut 1
2. Center front facing of left front — cut 1
3. Back neck facing — cut 1

## **INSTRUCTIONS:**

1. Apply fusible interfacing. Apply interfacing to seam allowances of pocket opening.
2. Sew darts on back. Press bulk towards center. Sew side backs to center back. Press the seam apart. Sew center back seam. Press the seam apart.
3. Sew pocket bag to center front and side front correspondingly. Sew side fronts to front, sewing the pocket bag edge at the same time. Press the seam apart, clipping into corner on side front. Press pocket towards center.
4. Sew side seams. Шов press apart. Sew shoulder seams. Шов press apart.
5. Sew elbow seam on sleeve. Press the seam apart. Sew front seam on sleeve. Sew sleeves into armholes. Sew on shoulder pads.
6. Sew outer stand collar into neckline. Clip into seam allowances and press seam apart.
7. Sew shoulder seams of central front facings and facings. Press the seam apart. Sew inner stand collar into neckline. Clip into seam allowances and press seam apart. Sew seams on lining, leaving an opening along one long side for turning in left side seam. Sew sleeves into armholes.
8. Pin center front facing to front, right sides together, and sew center edge and neckline. Start and stop

sewing exactly at the marked bottom line. Turn right side out and press. Baste together seam allowances of inner and outer stand collars. Sew lining to central front facings and to facings. Sew lining to lower edge of garment and lower edge of sleeve.

9. Make buttonholes and sew on buttons.

### TECHNICAL DRAWING:

