

## Jacket - Sewing Pattern #4970

Recommendations on fabric: natural/synthetic suiting fabrics .

You will also need: fusible interfacing; lining; shoulder pads; 4 buttons.

Seam allowances: Seam allowance on lower edge of sleeve 3, other seams - 1 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Center front - cut 2
4. Side front - cut 2
5. Center front facing - cut 2
6. Upper sleeve - cut 2
7. Lower sleeve - cut 2

8. Back neck facing – cut 1
9. Flap – cut 4
10. Pocket frame – cut 2
11. Front hem facing – cut 2
12. Back hem facing – cut 2

Lining:

1. Center front – cut 2
2. Center back – cut 2
3. Side back - cut 2
4. Side front – cut 2
5. Upper sleeve – cut 2
6. Lower sleeve – cut 2
7. Bigger pocket bag – cut 2
8. Smaller pocket bag – cut 2

Lining for front and back is cut using the pattern blocks for self fabric, except the areas of neckline facing, hem facing and center front facing.

Fusible interfacing:

1. Center front – cut 2
2. Center front facing – cut 2
3. Back neck facing - cut 1
4. Back hem facing – cut 2
5. Pocket frame – cut 2
6. Front hem facing – cut 2

Also apply fusible interfacing to: upper center back with armhole area, armhole of side back, seam allowance along hem of sleeve.

## INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side back to center back. Press seam apart. Sew the center back seam, press the seam apart.
3. Sew side front to center front. Press seam apart.
4. Sew flaps together by two, right sides together and sew along side and lower edges. Trim seam allowances, trim away corners, turn right side out and press. Mark the position of pockets with parallel lines. Fold pocket frame in half, wrong side together and press. Mark additional lines on pocket frame and on pocket flap for sewing it parallel to the fold. Sew bigger pocket bag to pocket flap. Sew pocket frame and pocket flap to front. Slash front along the line as marked on the pattern block. Snip diagonally toward end of stitching at 1-1.5 cm

from end of pocket opening. Turn the pocket frame and the pocket flap onto wrong side through the resulting opening, straighten edges. Fix corners of pockets in place by stitching a double stitch line from the wrong sides at the corners. Sew smaller pocket bag into the seam of pocket frame. Sew together edges of pocket bags.

5. Sew shoulder and side seams of jacket. Press Apart shoulder and side seams. Sew center collar seam. Press the seam allowances apart. Sew one-piece collar into neckline, clipping into seam allowance near corner. Clip seam allowances and press apart.

6. Sew the elbow seam of the sleeve and press it apart. Sew and press apart front sleeve seam. Sew sleeves into armholes matching notches. Sew shoulder pads.

7. Sew shoulder seams of facing and center front facing. Press the seam apart. Sew center collar seam. Press the seam allowances apart. Sew one-piece collar into neckline facings, clipping into seam allowance near corner. Clip seam allowances and press apart. Sew front hem facing to lower edge of center front facing. Press the seam apart. Sew center edge of back hem facing, press the seam apart. Sew side edges of hem facings. Press the seam apart.

8. Pin center front facing onto front right sides together and sew along hem, center front and neckline. Fold away center front facings and facings onto wrong side and press.

9. Sew the pieces from lining, leaving an opening for turning in front seam of right sleeve. Press lining.

10. Sew lining to center front facings, to back neckline facing, to hem facing, matching the seams on lining with seams on shell, and to hem of sleeve.

11. Turn jacket right side out through the opening in seam. Sew the opening in sleeve.

12. Make buttonholes and sew on buttons.

## **TECHNICAL DRAWING:**

