

Sewing Pattern — Pants 5110

Recommendations on fabric: wool or costume fabric

You will also need: fusing; lining; 1 zipper of 18 cm long; 2 zippers of 15 cm long; 1 button

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Front half - 2 details
2. Back half - 2 details
3. Belt - 1 detail
4. Pocket underlay piece - 2 details

Lining:

5. Front half - 2 details
6. Pocket bag - 4 details

Fusing: belt

INSTRUCTIONS:

1. Apply fusing to the half of the belt's width.
2. Sew darts, press depths towards center.
3. Apply fusing to wrong side of pocket openings. Make slash-pockets with zippers on front halves: fold pocket bag with front half right sides together stitch along marked lines. Cut the front half through, along between stitches, to ends of stitches - crosswise. You don't harm seams by that! Turn pocket bag through the slit onto wrong side and tack. Put zipper into the pocket slit and tack. Put decorative stitch along frame edge, stitching the zipper at the same time. Topstitch pocket underlay piece onto second pocket bag. Fold pocket bags, sew and tack to top and side edges of front halves.

4. Make and tack the tucks on lining details of front halves, press hem of lining inside, turn edges and stitch. Put lining onto front halves wrong sides together and tack along open edges.
5. Sew side seams, leaving a slit for zipper in upper part of left seam. Sew leg seams. Press apart the seam. Sew front and back center seams in one step. Press apart the seam from the top up to roundings.
6. Press seam allowances along zipper slit edges onto wrong side. Stitch the zipper under the edges of the slit so that zipper blade can not be seen.
7. Fold the belt in half lengthwise right sides together and overstitch ends; turn out and press. Put belt that is unfolded downwards, with its fused part onto waist edge of the garment from the right side and stitch. Straighten the belt, press inside open edge and stitch to main garment, continuing decorative stitch along all perimeter of the belt.
8. Press inside hem of the pants, turn edges and stitch.
9. Make buttonhole on right end of the belt, sew the button on left end.

TECHNICAL DRAWING:

