

Sewing Pattern — Dress 4274

Recommendations on fabric: natural or mixed fabric suitable for dresses.

You will also need: fusing, blind zipper, 4 buttons, decorative clasp of 6 cm wide

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: hem – 3 cm, all other seams - 1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Upper back part – 2 details
2. Lower back part – 2 details
3. Central upper front part – 1 detail
4. Side upper front part – 2 details
5. Lower front part – 1 detail
6. Yoke — 4 details
7. Front part of sleeve – 2 details
8. Back part of sleeve – 2 details
9. Cuff – 2 details
10. Flap – 4 details
11. Back neckline facing — 2 details
12. Front neckline facing – 1 detail
13. Belt loop – 1 detail
14. Belt – 1 detail

Fusing:

1. Cuff – 2 details
2. Flap – 2 details

3. Back neckline facing — 2 details
4. Front neckline facing – 1 detail

INSTRUCTIONS:

1. Apply fusing to details.
2. Sew darts on upper and lower back parts. Press darts to center seam. Sew upper and lower back parts, press seam allowances downwards and serge.
3. Apply fusing to wrong side of the vent on both of back part. Serge center edge of back part separately on each detail, serging the vent at the same time. Sew center edge of back part from zipper notch up to hem together with the vent. Slash away the corner of vent seam allowance on right part. Press apart allowances of center seam, pressing the slit for zipper and the vent. Topstitch seam allowances of the vent onto lower back part according to technical drawing. Sew in zipper.
4. Sew darts on front part, press depths upwards. Stitch side front part to central, press seam allowances to side edge and serge. Sew upper and bottom front parts, press seam allowances downwards and serge.
5. Fold details of the yoke right sides together and overstitch outer edge. Slash seam allowances on rounded parts, turn yoke right side out, press. Put decorative stitch at 0.7 cm. Serge a buttonhole according to marker. Put yokes onto front part and fix along neckline and armhole edges.
6. Sew upper edge of sleeve, press seam onto back part and serge. Press cuff in half lengthwise wrong sides together. Stitch cuff from wrong side of sleeve, press and serge seam allowances. Turn cuff onto right side, press.
7. Stitch back part of sleeve to the back. Slash seam allowances near the notch, serge upper part and press to the sleeve. Stitch front part of sleeve to the front. Slash seam allowances near the notch, serge upper part and press to the sleeve.
8. Fold details of the flap right sides together and overstitch outer edge. Slash seam allowances on rounded parts, slash away in corners, turn the flap right side out, press. Put decorative stitch at 0.7 cm. Serge a buttonhole according to marker. Put the flap onto front part and fix along side edge. Sew side seams, press seam onto back part and serge.
9. Cut bias tape of 4 cm wide and as long as lower part of the armhole + 6 cm. Fold bias tape in half lengthwise wrong sides together and press. Fold the bias tape with the edge of the armhole from right side, leaving tails, and overstitch. Turn bias tape onto wrong side, slash seams and topstitch along the fold onto main detail. Press the seam.
10. Sew shoulder seams of the facings. Press apart and serge seam allowances. Serge outer edge of the facings. Fold the dress with facing right sides together, leveling edges of neckline. Turn the facing away and pin to top edge of the dress, leaving 5mm to blind zipper edges. Turn seam allowances along zipper onto right side of the dress and pin to neckline edge, on top of facing. Overstitch neckline edge. Slash seam on rounded parts, turn details out and press. Topstitch seam allowances onto the facing. Tack facing to zipper tape.
11. Serge lower edge of the dress, turn inside onto wrong side and undersew with invisible stitches.
12. Serge one long edge of belt loop. Fold the belt loop in three layers and topstitch along long sides. Cut the belt loop into 2 details. Sew the belt loops on waist in side seams.
13. Fold belt in half lengthwise right sides together and overstitch along the long and short sides. Turn belt right side out, press. Serge short side. Put decorative stitch along the perimeter at 0.7 cm. Run and fasten the clasp.
14. Sew buttons according to buttonholes.

TECHNICAL DRAWING:

