

## Sewing Pattern — Dress 5859

Recommendations on fabric: natural or mixed knit fabric of low or medium stretchiness

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

<u>Seam allowances:</u> on hem and hem of sleeve – 1.5 cm, on back part and front part neckline edge – 1.5 cm, all other seams - 1 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING**:

### Main fabric:

- 1. Back part 2 details
- 2. Upper front part 1 detail
- 3. Lower front part 1 detail
- 4. Sleeve 2 details

#### Advice:

Knitted fabric details are sewn together with special elastic or narrow zig-zag stitch. When serging cut seam allowances to 0.6 - 0.8 cm. Seam allowance on turnup is stitched with twin needles to save stretchiness. Details also can be sewn together via 3 or 4 - threaded serger.

### **INSTRUCTIONS**:

- 1. Make free pleats on left side of lower front part's top edge. Fix pleats at 0.5 cm off the edge.
- 2. Sew together upper and lower front parts. Serge and press the seam upwards.
- 3. Sew center edge of back part. Serge and press the seam.
- 4. Sew shoulder seams of back part and of front part. Serge seams and press them towards back part. Serge neckline edge, press onto wrong side and topstitch.
- 5. Sew sleeves into open armholes, leveling notches. Serge and press the seams.
- 6. Sew side seams, sewing together sleeve edges at the same time. Serge seams and press them to back part.
- 7. Serge hem of garment and lower edge of sleeve. Fold to wrong side, press and topstitch.



# **TECHNICAL DRAWING:**

