

Sewing Pattern — Skirt 5840

Recommendations on fabric: natural or mixed thin woolen fabrics

You will also need: lining, fusing; 1 blind zipper; 1 button for belt, 3 buttons for vent.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm, hem of the garment - 3 cm, hem of lining on patterns – 1 cm, vent edge of right lower part – 6 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Center side part1 – 2 details
2. Center side part2 – 2 details
3. Lower side part1 – 2 details
4. Lower side part2 – 2 details
5. Lower left back part – 1 detail
6. Lower right back part – 1 detail
7. Upper back part – 2 details
8. Upper side part – 2 details
9. Front part – 1 detail
10. Belt – 1 detail

Lining:

1. Side back part – 2 details
2. Side front part – 2 details
3. Front part – 1 detail
4. Back part – 2 details

Fusing: Belt, vent

INSTRUCTIONS:

1. Sew center side parts 1 and 2. Serge the seam and press it to part 1. Sew details to upper side part. Serge the seam and press it upwards. Sew lower side parts 1 and 2. Serge the seam and press it to part 1. Sew upper and lower side parts. Serge the seam and press it upwards.
2. Apply fusing to wrong side of lower right and left back details. Mark a center seam line (vent fold line) on the right side. Press left part along vent fold line, on right part press only seam allowance of right side of the vent (6 cm) onto wrong side. Align details according to center seam and fix along top edge. Sew upper back parts from zipper marker up to lower edge. Press seams apart and serge. Sew upper and lower back parts. Press seams upwards and serge. Sew in zipper, press the seam.
3. Sew front and back princess edges. Press seams towards center of front part and center of back part correspondingly and serge.
4. Sew, serge and press details of lining. On center edge of lining sew only short section between notches. Stitch closure seam allowances to zipper tape. Fix lining to the garment along top edge.
5. Apply fusing to belt. Press belt along in the center wrong sides together. Stitch outer side of the belt to top edge of the skirt, over stitching corners of the belt at the same time. Turn inner edge of the belt inside and topstitch into belt connecting seam. Make buttonhole and sew a button.
6. Serge lower edge of the skirt on main garment. Turn inside, press and topstitch onto the skirt with invisible stitch. Serge buttonholes on the vent. Turn hem of lining twice inside at 1 cm and topstitch.
7. Turn the skirt onto wrong side. Fix main fabric and lining details along center seam, move lining slightly upwards by that. Cut out a square on left part of lining according to markers and slash the corner. Turn edges of lining inside and sew to vent sides.
8. Sew buttons on the vent.

TECHNICAL DRAWING:

