

Recommendations on fabric: natural or mixed light-weight fabric suitable for blouses, e.g. chiffon.

You will also need: fusible interfacing.

Seam allowances: hem – 1.5 cm, other seams – 1 cm.

**Note on seam allowances:**

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

**Note on length of fabric:**

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*




## CUTTING:

### Main fabric:

1. Back - cut 2 (A)
2. Front - cut 1 (B)
3. Front slit band/facing - cut 2 (E)
4. Back neck band/facing - cut 2 (C)
5. Front neck band/facing - cut 2 (D)
6. Back armhole band/facing - cut 4 (F)
7. Front armhole band/facing - cut 4 (G)

### Fusible interfacing:

1. Front slit facing - cut 1 (E)
2. Back neck facing - cut 1 (C)
3. Front neck facing - cut 1 (D)
4. Back armhole facing - cut 2 (F)
5. Front armhole facing - cut 2 (G)



---

**INSTRUCTIONS:**

1. Apply fusible interfacing to facings.
2. Sew center back seam. Serge and press seam towards left side.
3. Sew bust darts and press downwards.
4. Pin front slit band and facings right sides together and sew slit edge. Trim seam, turn right side out, straighten and press. Sew outer part of band to front, press seam towards facing. Turn edge of facing under, and topstitch into outer band connecting seam.
5. Sew outer edge of back neck band to back, press seam towards band. Sew outer edge of front neck band to front, press seam towards band.
6. Sew back armhole band to f back armhole press seam towards band. Sew front armhole band to front, press seam towards band
7. Sew side and shoulder seams, serge and press seams toward back.
8. Sew shoulder seams of front/back neck facings, press seams open. Pin facings to neckline right sides together and sew along neckline. Clip seam on curves, turn facing to wrong side. Turn free edge of inner neck facing under, and topstitch into outer band connecting seam.
9. Sew side and shoulder seams of front/back armhole facings, press seams open. Pin facing to armhole right sides together and sew along armhole. Clip seam on curves, turn facing to wrong side. Turn under free edge of inner armhole facing and topstitch into outer band connecting seam.
10. Serge lower edge of top, turn under, press, and topstitch.

TECHNICAL DRAWING:

