

Bomber With Push Buttons - Sewing Pattern #2752

Recommendations on fabric: thick natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 7 push buttons.

Seam allowances: all seams 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 1 on fold
2. Back yoke - cut 1
3. Yoke - cut 2
4. Front yoke - cut 2
5. Front - cut 2
6. Center front facing - cut 2
7. Collar - cut 2

8. Back neck facing – cut 1
9. Sleeve – cut 2

Knit band:

1. Belt – cut 1 on fold
2. Cuff – cut 2

Fusible interfacing:

1. Center front facing – cut 2
2. Back neck facing – cut 1
3. Collar – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew back yoke to back, press seam allowances towards top and serge. Sew yoke to back yoke, press seam allowances at yoke, serge.
3. Sew front darts, press bulk towards top. Sew front yoke to front, press seam allowances at yoke, serge. Sew front to yoke, press seam allowances at yoke, serge.
4. Sew side seams, press towards the back and serge.
5. Fold the belt in half lengthwise, wrong sides together, and press. Sew belt to lower edge of garment, slightly stretching it, and slashing front in the corner.
6. Pin upper collar to lower collar and sew the corners and the outer edge up to notch. Trim away corners, snip into seam allowance near the mark. Turn the collar right side out, straighten and press.
7. Sew side seams of back neckline facing and central front facings, press seam apart. Serge the outer edge.
8. Place center front facing onto front right sides together, pin together and sew along the front center edge and the lower edge up to the beginning of the belt. Sew upwards up to the notch marking the end of collar seam. Turn center front facings right side out, straighten seams. Topstitch front at center front facing along the seam of belt.
9. Sew lower collar into the neckline of the main piece, sew upper collar into the neckline of back facing and center front facing. Press seam allowances of the collar seam apart and slipstitch them together close to the seam.
10. Sew sleeve seam, press towards back and serge. Sew sleeves into armholes, serge and press.

11. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise and press right side out. Sew the cuff to the sleeve, slightly stretching it, serge and press.

12. Install the upper parts of the push buttons on the right front, install the lower parts of the push buttons on the left front.

Tip: you may use a ready belt and ready cuffs in knit band.

TECHNICAL DRAWING:

