

## Sewing Pattern — Blouse 5693

<u>Recommendations on fabric</u>: natural/mixed fabric or fabric suitable for shirts

You will also need: fusing; 9 snaps; 2 decorative clasps

If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowance: 1 cm for all seams, 2 cm for garment/sleeve hems, 2 cm for pocket's upper edge.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING**:

#### Main fabric:

- 1. Back part 2 pieces
- 2. Right front part 1 piece
- 3. Left front part 1 piece
- 4. Collar 2 pieces
- 5. Stand-up collar 2 pieces
- 6. Sleeve 2 pieces
- 7. Right placket 1 piece
- 8. Left upper placket 1 piece
- 9. Left lower placket 1 piece
- 10. Flap 4 pieces
- 11. Pocket 2 pieces
- 12. Long half-belt 2 pieces
- 13. Short half-belt 2 pieces

Fusing: left lower/upper plackets, outer collar, outer stand-up collar, outer flap



#### **INSTRUCTIONS:**

- 1. Apply the fusing to wrong side of Продублировать клеевой прокладкой left lower/upper plackets, outer collar, outer stand-up collar and 2nd flaps.
- 2. Stitch front/back darts. Press darts toward centers.
- 3. Fold half-belts along the center wrong side out and overstitch one long/one short edges. Cut allowances, turn details right side out and press them. Make decorative stitch along half-belt edge. Stitch short half-belt to armhole as marked.
- 4. Lay flaps right sides together and overstitch them. Cut flap corners' allowances and turn the detail right side out. Press seams. Neaten flap's free edge. Mark upper front pocket place. Stitch the flap to front part, fold it under and topstitch.
- 5. Make inverted pleats into pockets. Press pocket's upper allowance into wrong side, fold it under and topstitch. Press pocket's side/lower allowances into wrong side. Lay pockets on front part as marked. Topstitch patch pockets.
- 6. Lay collars right sides together and overstitch them along ends and collar fall. Slash and turn corners right side out. Stitch stand-ups together inserting the collar between them. Turn the detail right side out and press it.
- 7. Press right placket's/left packets' outer edges into wrong side. Stitch left lower placket to left upper placket. Lay left/right plackets on front parts right sides together and overstitch along front edgings. Stitch plackets' lower edges to front part strictly along marked hem line. Turn front edgings right side out, press seams. Topstitch plackets' inner edge on front parts. Fix plackets at front neckline.
- 8. Fold long half-belt's raw edge under and topstitch it above the flap along the seam joining the placket.
- 9. Stitch blouse shoulder/side seams. Press seams backward and neaten them.
- 10. Stitch inner stand-up (with the collar) into neckline, fold outer stand-up's open edge and topstitch along the seam joining inner stand-up collar. Make decorative stitch along the collar.
- 11. Stitch sleeve edges and neaten them. Stitch sleeves in easing them along sleeve caps.
- 12. Neaten garment/sleeve hems, press them into wrong side and topstitch.
- 13. Pierce upper snaps into right front part, set lower snaps on left front part. Fix clasps on short half-belts, pieces eyelets into long half-belts.



# **TECHNICAL DRAWING:**

