

Sweatshirt With Pockets - Sewing Pattern #2037

Recommendations on fabric: thin fleece, footer or natural/mixed thick knit fabric of small stretchiness.

You will also need: lining, knit fabric of high stretchiness.

Seam allowances: all seams 1 cm.

Note on seam allowances:


- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

Note on working with stretchy fabric:

Knitted fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hems can be stitched with twin needles to save stretchiness. Pieces can also be sewn together with a serger. When serging, cut seam allowances to 0.6 – 0.8 cm.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Front – cut 1 on fold
2. Front side – cut 2
3. Back – cut 1 on fold

4. Sleeve – cut 2

Knit fabric of high stretchiness:

1. Neckline facing – cut 1
2. Hem facing – cut 2
3. Cuff – cut 2

Lining:

1. Pocket bag – cut 4

INSTRUCTIONS:

1. Sew pocket bags to front and side front. Serge the seam allowances. Sew side front to front, sewing the pocket bags at the same time. Serge seams and press towards center.
2. Sew shoulder seams. Serge seams and press towards back.
3. Sew sleeves into armholes. Serge the seam allowances and press onto sleeve. Sew side edge and sleeve seam continuously. Serge and press towards back.
4. Sew neckline facing into a ring. Press the seam apart. Pin together in half lengthwise and press. Sew facing to neckline slightly stretching it. Serge the seam allowances and press towards facing.
5. Sew cuff into a ring. Press the seam apart. Pin together in half lengthwise and press. Sew cuff to lower edge of sleeve slightly stretching it. Serge the seam allowances and press towards facing.
6. Sew hem facing into a ring. Press the seam apart. Pin together in half lengthwise and press. Sew facing to front and back slightly stretching it. Serge the seam allowances and press towards facing.

TECHNICAL DRAWING:

