

## Top With Lace Yoke - Sewing Pattern #2351

Recommendations on fabric: natural/mixed knit fabric of small/medium stretchiness, stable stretchy lace.

Seam allowances: all seams 1 cm. Seam allowance along hem – 2 cm. Seam allowance along hem yokes – 0 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

### Note on working with stretchy fabric:

Knitted fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hems can be stitched with twin needles to save stretchiness. Pieces can also be sewn together with a serger. When serging, cut seam allowances to 0.6 – 0.8 cm.



## CUTTING:

### Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back – cut 1 on fold
2. Front - cut 1 on fold

Main fabric 1:

1. Yoke – cut 1 on fold

## **INSTRUCTIONS:**

1. Serge upper edge of front, turn inside and topstitch. Pin yoke, right side up, onto front, and match with the lower marked line. Topstitch along the upper marked line from the right side.
2. Sew right shoulder seam. Serge and press towards back.
3. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of neckline + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to neckline from the right side and sew. Clip into seam allowances. Fold bias tape onto wrong side and topstitch onto main piece along the seam. Press seam.
4. Sew left shoulder seam. Serge and press towards back.
5. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of armhole + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to armhole edge from the right side and sew. Clip into seam allowances. Fold bias tape onto wrong side and topstitch onto main piece along the seam. Press seam.
6. Sew side seams, press towards the back and serge.
7. Serge lower edge of garment, press onto wrong side and topstitch.

## **TECHNICAL DRAWING:**

